

Distribution Category:
Mathematics and
Computer Science (UC-405)

ARGONNE NATIONAL LABORATORY
9700 South Cass Avenue
Argonne, IL 60439

ANL-00

MPICH Model MPI Implementation Reference Manual

Draft

by

*William Gropp
Ewing Lusk Mathematics and Computer Science Division
Argonne National Laboratory*

*Nathan Doss
Anthony Skjellum
Department of Computer Science
Mississippi State University*

January 13, 2003

This work was supported by the Mathematical, Information, and Computational Sciences Division subprogram of the Office of Computational and Technology Research, U.S. Department of Energy, under Contract W-31-109-Eng-38.

Contents

1	Introduction	1
2	MPI routines	1
3	MPE routines	199

1 Introduction

This document contains detailed documentation on the routines that are part of the MPICH model MPI implementation.

As an alternate to this manual, the reader should consider using the script `mpiman`; this is a script that uses `xman` to provide a X11 Window System interface to the data in this manual.

2 MPI routines

MPIO_Request_c2f	MPIO_Request_c2f
------------------	------------------

MPIO_Request_c2f — Translates a C I/O-request handle to a Fortran I/O-request handle

Synopsis

```
MPI_Fint MPIO_Request_c2f(MPIO_Request request)
```

Input Parameters

request C I/O-request handle (handle)

Return Value

Fortran I/O-request handle (integer)

Location

```
./romio/mpi-io/ioreq_c2f.c
```

MPIO_Request_f2c	MPIO_Request_f2c
------------------	------------------

MPIO_Request_f2c — Translates a Fortran I/O-request handle to a C I/O-request handle

Synopsis

```
MPIO_Request MPIO_Request_f2c(MPI_Fint request)
```

Input Parameters

request Fortran I/O-request handle (integer)

Return Value

C I/O-request handle (handle)

Location

```
./romio/mpi-io/ioreq_f2c.c
```

MPIO_Test**MPIO_Test**

MPIO_Test — Test the completion of a nonblocking read or write

Synopsis

```
int MPIO_Test(MPIO_Request *request, int *flag, MPI_Status *status)
```

Input Parameters

request request object (handle)

Output Parameters

flag	true if operation completed (logical)
status	status object (Status)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./romio/mpi-io/iotest.c
```

MPIO_Wait**MPIO_Wait**

MPIO_Wait — Waits for the completion of a nonblocking read or write

Synopsis

```
int MPIO_Wait(MPIO_Request *request, MPI_Status *status)
```

Input Parameters

request request object (handle)

Output Parameters

status status object (Status)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./romio/mpi-io/iowait.c`

MPI_Abort

MPI_Abort

MPI_Abort — Terminates MPI execution environment

Synopsis

```
int MPI_Abort( MPI_Comm comm, int errorcode )
```

Input Parameters

comm communicator of tasks to abort
errorcode error code to return to invoking environment

Notes

Terminates all MPI processes associated with the communicator **comm**; in most systems (all to date), terminates *all* processes.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./src/env/abort.c`

MPI_Address

MPI_Address

MPI_Address — Gets the address of a location in memory

Synopsis

```
int MPI_Address( void *location, MPI_Aint *address)
```

Input Parameters

location location in caller memory (choice)

Output Parameter

address address of location (integer)

Note

This routine is provided for both the Fortran and C programmers. On many systems, the address returned by this routine will be the same as produced by the C & operator, but this is not required in C and may not be true of systems with word- rather than byte-oriented instructions or systems with segmented address spaces.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./src/pt2pt/address.c
```

MPI_Allgather

MPI_Allgather

MPI_Allgather — Gathers data from all tasks and distribute it to all

Synopsis

```
int MPI_Allgather ( void *sendbuf, int sendcount, MPI_Datatype sendtype,
                   void *recvbuf, int recvcount, MPI_Datatype recvtype,
                   MPI_Comm comm )
```

Input Parameters

sendbuf	starting address of send buffer (choice)
sendcount	number of elements in send buffer (integer)
sendtype	data type of send buffer elements (handle)
recvcount	number of elements received from any process (integer)
recvtype	data type of receive buffer elements (handle)
comm	communicator (handle)

Output Parameter

recvbuf address of receive buffer (choice)

Notes

The MPI standard (1.0 and 1.1) says that

The jth block of data sent from each process is received by every process and placed in the jth block of the buffer **recvbuf**.

This is misleading; a better description is

The block of data sent from the jth process is received by every process and placed in the jth block of the buffer **recvbuf**.

This text was suggested by Rajeev Thakur.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted MPI_Datatype (see **MPI_Type_commit**).

MPI_ERR_BUFFER

Invalid buffer pointer. Usually a null buffer where one is not valid.

Location

`./src/coll/allgather.c`

MPI_Allgatherv

MPI_Allgatherv

MPI_Allgatherv — Gathers data from all tasks and deliver it to all

Synopsis

```
int MPI_Allgatherv ( void *sendbuf, int sendcount, MPI_Datatype sendtype,
                     void *recvbuf, int *recvcounts, int *displs,
                     MPI_Datatype recvtype, MPI_Comm comm )
```

Input Parameters

sendbuf	starting address of send buffer (choice)
sendcount	number of elements in send buffer (integer)
sendtype	data type of send buffer elements (handle)
recvcounts	integer array (of length group size) containing the number of elements that are received from each process
displs	integer array (of length group size). Entry <i>i</i> specifies the displacement (relative to recvbuf) at which to place the incoming data from process <i>i</i>
recvtype	data type of receive buffer elements (handle)
comm	communicator (handle)

Output Parameter

recvbuf	address of receive buffer (choice)
----------------	------------------------------------

Notes

The MPI standard (1.0 and 1.1) says that

The *j*th block of data sent from each process is received by every process and placed in the *j*th block of the buffer **recvbuf**.

This is misleading; a better description is

The block of data sent from the *j*th process is received by every process and placed in the *j*th block of the buffer **recvbuf**.

This text was suggested by Rajeev Thakur.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_ERR_BUFFER

Invalid buffer pointer. Usually a null buffer where one is not valid.

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted MPI_Datatype (see [MPI_Type_commit](#)).

Location

[./src/coll/allgatherv.c](#)

MPI_Allreduce**MPI_Allreduce**

MPI_Allreduce — Combines values from all processes and distribute the result back to all processes

Synopsis

```
int MPI_Allreduce ( void *sendbuf, void *recvbuf, int count,
                    MPI_Datatype datatype, MPI_Op op, MPI_Comm comm )
```

Input Parameters

sendbuf	starting address of send buffer (choice)
count	number of elements in send buffer (integer)
datatype	data type of elements of send buffer (handle)
op	operation (handle)
comm	communicator (handle)

Output Parameter

recvbuf	starting address of receive buffer (choice)
----------------	---

Notes for Fortran

All MPI routines in Fortran (except for [MPI_WTIME](#) and [MPI_WTICK](#)) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., [MPI_Datatype](#), [MPI_Comm](#)) are of type **INTEGER** in Fortran.

Notes on collective operations

The reduction functions ([MPI_Op](#)) do not return an error value. As a result, if the functions detect an error, all they can do is either call [MPI_Abort](#) or silently skip the problem. Thus, if you change the error handler from [MPI_ERRORS_ARE_FATAL](#) to something else, for example, [MPI_ERRORS_RETURN](#), then no error may be indicated.

The reason for this is the performance problems in ensuring that all collective routines return the same error value.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_ERR_BUFFER`

Invalid buffer pointer. Usually a null buffer where one is not valid.

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

`MPI_ERR_OP`

Invalid operation. MPI operations (objects of type `MPI_Op`) must either be one of the predefined operations (e.g., `MPI_SUM`) or created with `MPI_Op_create`.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

Location

`./src/coll/allreduce.c`

`MPI_Alltoall`

`MPI_Alltoall`

`MPI_Alltoall` — Sends data from all to all processes

Synopsis

```
int MPI_Alltoall( void *sendbuf, int sendcount, MPI_Datatype sendtype,
                  void *recvbuf, int recvcnt, MPI_Datatype recvtype,
                  MPI_Comm comm )
```

Input Parameters

<code>sendbuf</code>	starting address of send buffer (choice)
<code>sendcount</code>	number of elements to send to each process (integer)
<code>sendtype</code>	data type of send buffer elements (handle)
<code>recvcount</code>	number of elements received from any process (integer)
<code>recvtype</code>	data type of receive buffer elements (handle)
<code>comm</code>	communicator (handle)

Output Parameter

<code>recvbuf</code>	address of receive buffer (choice)
----------------------	------------------------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted `MPI_Datatype` (see `MPI_Type_commit`).

`MPI_ERR_BUFFER`

Invalid buffer pointer. Usually a null buffer where one is not valid.

Location

`./src/coll/alltoall.c`

`MPI_Alltoallv`

`MPI_Alltoallv`

`MPI_Alltoallv` — Sends data from all to all processes, with a displacement

Synopsis

```
int MPI_Alltoallv (
    void *sendbuf,
    int *sendcnts,
    int *sdispls,
    MPI_Datatype sendtype,
    void *recvbuf,
    int *recvcnts,
    int *rdispls,
    MPI_Datatype recvtype,
    MPI_Comm comm )
```

Input Parameters

<code>sendbuf</code>	starting address of send buffer (choice)
----------------------	--

sendcounts	integer array equal to the group size specifying the number of elements to send to each processor
sdispls	integer array (of length group size). Entry <i>j</i> specifies the displacement (relative to sendbuf from which to take the outgoing data destined for process <i>j</i>)
sendtype	data type of send buffer elements (handle)
recvcounts	integer array equal to the group size specifying the maximum number of elements that can be received from each processor
rdispls	integer array (of length group size). Entry <i>i</i> specifies the displacement (relative to recvbuf at which to place the incoming data from process <i>i</i>)
recvtype	data type of receive buffer elements (handle)
comm	communicator (handle)

Output Parameter

recvbuf address of receive buffer (choice)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted **MPI_Datatype** (see **MPI_Type_commit**).

MPI_ERR_BUFFER

Invalid buffer pointer. Usually a null buffer where one is not valid.

Location

`./src/coll/alltoallv.c`

MPI_Attr_delete

MPI_Attr_delete

MPI_Attr_delete — Deletes attribute value associated with a key

Synopsis

```
int MPI_Attr_delete ( MPI_Comm comm, int keyval )
```

Input Parameters

comm	communicator to which attribute is attached (handle)
keyval	The key value of the deleted attribute (integer)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_ARG

This error class is associated with an error code that indicates that an attempt was made to free one of the permanent keys.

Location

`./src/context/attr_delval.c`

MPI_Attr_get

MPI_Attr_get

MPI_Attr_get — Retrieves attribute value by key

Synopsis

```
int MPI_Attr_get (
    MPI_Comm comm,
    int keyval,
    void *attr_value,
    int *flag )
```

Input Parameters

comm	communicator to which attribute is attached (handle)
keyval	key value (integer)

Output Parameters

attr_value	attribute value, unless flag = false
flag	true if an attribute value was extracted; false if no attribute is associated with the key

Notes

Attributes must be extracted from the same language as they were inserted in with **MPI_ATTR_PUT**. The notes for C and Fortran below explain why.

Notes for C

Even though the **attr_value** argument is declared as **void ***, it is really the address of a void pointer. See the rationale in the standard for more details.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

The **attr_value** in Fortran is a pointer to a Fortran integer, not a pointer to a **void ***.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_OTHER

Other error; the error code associated with this error indicates an attempt to use an invalid keyval.

Location

`./src/context/attr_getval.c`

MPI_Attr_put**MPI_Attr_put**

MPI_Attr_put — Stores attribute value associated with a key

Synopsis

```
int MPI_Attr_put ( MPI_Comm comm, int keyval, void *attr_value )
```

Input Parameters

comm	communicator to which attribute will be attached (handle)
keyval	key value, as returned by MPI_KEYVAL_CREATE (integer)
attribute_val	attribute value

Notes

Values of the permanent attributes **MPI_TAG_UB**, **MPI_HOST**, **MPI_IO**, and **MPI_WTIME_IS_GLOBAL** may not be changed.

The type of the attribute value depends on whether C or Fortran is being used. In C, an attribute value is a pointer (**void ***); in Fortran, it is a single integer (*not* a pointer, since Fortran has no pointers and there are systems for which a pointer does not fit in an integer (e.g., any > 32 bit address system that uses 64 bits for Fortran **DOUBLE PRECISION**).

If an attribute is already present, the delete function (specified when the corresponding keyval was created) will be called.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_OTHER

Other error; the error code associated with this error indicates an attempt to use an invalid keyval.

MPI_ERR_ARG

This error class is associated with an error code that indicates that an attempt was made to free one of the permanent keys.

See Also

`MPI_Attr_get`, `MPI_Keyval_create`, `MPI_Attr_delete`

Location

`./src/context/attr_putval.c`

MPI_Barrier

MPI_Barrier

MPI_Barrier — Blocks until all process have reached this routine.

Synopsis

```
int MPI_Barrier (
    MPI_Comm comm )
```

Input Parameters

comm communicator (handle)

Notes

Blocks the caller until all group members have called it; the call returns at any process only after all group members have entered the call.

Algorithm

If the underlying device cannot do better, a tree-like or combine algorithm is used to broadcast a message wto all members of the communicator. We can modify this to use "blocks" at a later time (see `MPI_Bcast`).

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

Location

`./src/coll/barrier.c`

`MPI_Bcast`

`MPI_Bcast`

`MPI_Bcast` — Broadcasts a message from the process with rank "root" to all other processes of the group.

Synopsis

```
int MPI_Bcast ( void *buffer, int count, MPI_Datatype datatype, int root,
                MPI_Comm comm )
```

Input/output Parameters

<code>buffer</code>	starting address of buffer (choice)
<code>count</code>	number of entries in buffer (integer)
<code>datatype</code>	data type of buffer (handle)
<code>root</code>	rank of broadcast root (integer)
<code>comm</code>	communicator (handle)

Algorithm

If the underlying device does not take responsibility, this function uses a tree-like algorithm to broadcast the message to blocks of processes. A linear algorithm is then used to broadcast the message from the first process in a block to all other processes. `MPIR_BCAST_BLOCK_SIZE` determines the size of blocks. If this is set to 1, then this function is equivalent to using a pure tree algorithm. If it is set to the size of the group or greater, it is a pure linear algorithm. The value should be adjusted to determine the most efficient value on different machines.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted `MPI_Datatype` (see `MPI_Type_commit`).

`MPI_ERR_BUFFER`

Invalid buffer pointer. Usually a null buffer where one is not valid.

`MPI_ERR_ROOT`

Invalid root. The root must be specified as a rank in the communicator. Ranks must be between zero and the size of the communicator minus one.

Location

`./src/coll/bcast.c`

`MPI_Bsend`

`MPI_Bsend`

`MPI_Bsend` — Basic send with user-specified buffering

Synopsis

```
int MPI_Bsend(
    void *buf,
    int count,
    MPI_Datatype datatype,
    int dest,
    int tag,
    MPI_Comm comm )
```

Input Parameters

<code>buf</code>	initial address of send buffer (choice)
<code>count</code>	number of elements in send buffer (nonnegative integer)
<code>datatype</code>	datatype of each send buffer element (handle)
<code>dest</code>	rank of destination (integer)

tag	message tag (integer)
comm	communicator (handle)

Notes

This send is provided as a convenience function; it allows the user to send messages without worrying about where they are buffered (because the user *must* have provided buffer space with **MPI_Buffer_attach**).

In deciding how much buffer space to allocate, remember that the buffer space is not available for reuse by subsequent **MPI_Bsend**s unless you are certain that the message has been received (not just that it should have been received). For example, this code does not allocate enough buffer space

```
MPI_Buffer_attach( b, n*sizeof(double) + MPI_BSEND_OVERHEAD );
for (i=0; i<m; i++) {
    MPI_Bsend( buf, n, MPI_DOUBLE, ... );
}
```

because only enough buffer space is provided for a single send, and the loop may start a second **MPI_Bsend** before the first is done making use of the buffer.

In C, you can force the messages to be delivered by

```
MPI_Buffer_detach( &b, &n );
MPI_Buffer_attach( b, n );
```

(The **MPI_Buffer_detach** will not complete until all buffered messages are delivered.)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted **MPI_Datatype** (see **MPI_Type_commit**).

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_SOURCE`.

MPI_ERR_TAG

Invalid tag argument. Tags must be non-negative; tags in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_TAG`. The largest tag value is available through the attribute `MPI_TAG_UB`.

See Also

`MPI_Buffer_attach`, `MPI_Ibsend`, `MPI_Bsend_init`

Location

`./src/pt2pt/bsend.c`

MPI_Bsend_init**MPI_Bsend_init**

MPI_Bsend_init — Builds a handle for a buffered send

Synopsis

```
int MPI_Bsend_init( void *buf, int count, MPI_Datatype datatype, int dest,
                    int tag, MPI_Comm comm, MPI_Request *request )
```

Input Parameters

buf	initial address of send buffer (choice)
count	number of elements sent (integer)
datatype	type of each element (handle)
dest	rank of destination (integer)
tag	message tag (integer)
comm	communicator (handle)

Output Parameter

request	communication request (handle)
----------------	--------------------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

`MPI_ERR_RANK`

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_SOURCE`.

`MPI_ERR_TAG`

Invalid tag argument. Tags must be non-negative; tags in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_TAG`. The largest tag value is available through the attribute `MPI_TAG_UB`.

Location

`./src/pt2pt/bsend_init.c`

`MPI_Buffer_attach`

`MPI_Buffer_attach`

`MPI_Buffer_attach` — Attaches a user-defined buffer for sending

Synopsis

```
int MPI_Buffer_attach( void *buffer, int size )
```

Input Parameters

<code>buffer</code>	initial buffer address (choice)
<code>size</code>	buffer size, in bytes (integer)

Notes

The size given should be the sum of the sizes of all outstanding Bsends that you intend to have, plus a few hundred bytes for each Bsend that you do. For the purposes of calculating size, you should use `MPI_Pack_size`. In other words, in the code

```

MPI_Buffer_attach( buffer, size );
MPI_Bsend( ... , count=20, datatype=type1, ... );
...
MPI_Bsend( ... , count=40, datatype=type2, ... );

```

the value of `size` in the `MPI_Buffer_attach` call should be greater than the value computed by

```

MPI_Pack_size( 20, type1, comm, &s1 );
MPI_Pack_size( 40, type2, comm, &s2 );
size = s1 + s2 + 2 * MPI_BSEND_OVERHEAD;

```

The `MPI_BSEND_OVERHEAD` gives the maximum amount of space that may be used in the buffer for use by the BSEND routines in using the buffer. This value is in `mpi.h` (for C) and `mpif.h` (for Fortran).

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_BUFFER`

Invalid buffer pointer. Usually a null buffer where one is not valid.

`MPI_ERR_INTERN`

An internal error has been detected. This is fatal. Please send a bug report to `mpi-bugs@mcs.anl.gov`.

See Also

`MPI_Buffer_detach`, `MPI_Bsend`

Location

`./src/pt2pt/bufattach.c`

MPI_Buffer_detach

MPI_Buffer_detach

MPI_Buffer_detach — Removes an existing buffer (for use in `MPI_Bsend` etc)

Synopsis

```
int MPI_Buffer_detach(
    void *bufferptr,
    int *size )
```

Output Parameters

buffer	initial buffer address (choice)
size	buffer size, in bytes (integer)

Notes

The reason that `MPI_Buffer_detach` returns the address and size of the buffer being detached is to allow nested libraries to replace and restore the buffer. For example, consider

```
int size, mysize, idummy;
void *ptr, *myptr, *dummy;
MPI_Buffer_detach( &ptr, &size );
MPI_Buffer_attach( myptr, mysize );
...
... library code ...
...
MPI_Buffer_detach( &dummy, &idummy );
MPI_Buffer_attach( ptr, size );
```

This is much like the action of the Unix signal routine and has the same strengths (it is simple) and weaknesses (it only works for nested usages).

Note that for this approach to work, `MPI_Buffer_detach` must return `MPI_SUCCESS` even when there is no buffer to detach. In that case, it returns a size of zero. The MPI 1.1 standard for `MPI_BUFFER_DETACH` contains the text

```
The statements made in this section describe the behavior of MPI for buffered-mode sends. When no buffer is currently associated, MPI behaves as if a zero-sized buffer is associated with the process.
```

This could be read as applying only to the various `Bsend` routines. This implementation takes the position that this applies to `MPI_BUFFER_DETACH` as well.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

The Fortran binding for this routine is different. Because Fortran does not have pointers, it is impossible to provide a way to use the output of this routine to exchange buffers. In this case, only the size field is set.

Notes for C

Even though the `bufferptr` argument is declared as `void *`, it is really the address of a void pointer. See the rationale in the standard for more details.

Location

`./src/pt2pt/buffree.c`

MPI_Cancel

MPI_Cancel

MPI_Cancel — Cancels a communication request

Synopsis

```
int MPI_Cancel( MPI_Request *request )
```

Input Parameter

request	communication request (handle)
----------------	--------------------------------

Note

Cancel has only been implemented for receive requests; it is a no-op for send requests. The primary expected use of **MPI_Cancel** is in multi-buffering schemes, where speculative **MPI_Irecv**s are made. When the computation completes, some of these receive requests may remain; using **MPI_Cancel** allows the user to cancel these unsatisfied requests.

Cancelling a send operation is much more difficult, in large part because the send will usually be at least partially complete (the information on the tag, size, and source are usually sent immediately to the destination). As of version 1.2.0, MPICH supports cancelling of sends. Users are advised that cancelling a send, while a local operation (as defined by the MPI standard), is likely to be expensive (usually generating one or more internal messages).

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Null Handles

The MPI 1.1 specification, in the section on opaque objects, explicitly

disallows freeing a null communicator. The text from the standard is

A null handle argument is an erroneous IN argument in MPI calls, unless an exception is explicitly stated in the text that defines the function. Such exception is allowed for handles to request objects in Wait and Test calls (sections Communication Completion and Multiple Completions). Otherwise, a null handle can only be passed to a function that allocates a new object and returns a reference to it in the handle.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_REQUEST`

Invalid `MPI_Request`. Either null or, in the case of a `MPI_Start` or `MPI_Startall`, not a persistent request.

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

Location

`./src/pt2pt/cancel.c`

<code>MPI_Cart_coords</code>	<code>MPI_Cart_coords</code>
<code>MPI_Cart_coords</code> — Determines process coords in cartesian topology given rank in group	

Synopsis

```
int MPI_Cart_coords ( MPI_Comm comm, int rank, int maxdims, int *coords )
```

Input Parameters

<code>comm</code>	communicator with cartesian structure (handle)
<code>rank</code>	rank of a process within group of <code>comm</code> (integer)
<code>maxdims</code>	length of vector <code>coords</code> in the calling program (integer)

Output Parameter

<code>coords</code>	integer array (of size <code>ndims</code>) containing the Cartesian coordinates of specified process (integer)
---------------------	---

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_TOPOLOGY`

Invalid topology. Either there is no topology associated with this communicator, or it is not the correct type (e.g., `MPI_CART` when expecting `MPI_GRAPH`).

`MPI_ERR_RANK`

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_SOURCE`.

`MPI_ERR_DIMS`

Illegal dimension argument. A dimension argument is null or its length is less than or equal to zero.

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

Location

`./src/topol/cart_coords.c`

`MPI_Cart_create`

`MPI_Cart_create`

`MPI_Cart_create` — Makes a new communicator to which topology information has been attached

Synopsis

```
int MPI_Cart_create ( MPI_Comm comm_old, int ndims, int *dims, int *periods,
                      int reorder, MPI_Comm *comm_cart )
```

Input Parameters

<code>comm_old</code>	input communicator (handle)
<code>ndims</code>	number of dimensions of cartesian grid (integer)
<code>dims</code>	integer array of size <code>ndims</code> specifying the number of processes in each dimension
<code>periods</code>	logical array of size <code>ndims</code> specifying whether the grid is periodic (true) or not (false) in each dimension
<code>reorder</code>	ranking may be reordered (true) or not (false) (logical)

Output Parameter

<code>comm_cart</code>	communicator with new cartesian topology (handle)
------------------------	---

Algorithm

We ignore `reorder` info currently.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_TOPOLOGY`

Invalid topology. Either there is no topology associated with this communicator, or it is not the correct type (e.g., `MPI_CART` when expecting `MPI_GRAPH`).

`MPI_ERR_DIMS`

Illegal dimension argument. A dimension argument is null or its length is less than or equal to zero.

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

Location

`./src/topol/cart_create.c`

`MPI_Cart_get`

`MPI_Cart_get`

`MPI_Cart_get` — Retrieves Cartesian topology information associated with a communicator

Synopsis

```
int MPI_Cart_get (
    MPI_Comm comm,
    int maxdims,
    int *dims,
    int *periods,
    int *coords )
```

Input Parameters

comm	communicator with cartesian structure (handle)
maxdims	length of vectors dims , periods , and coords in the calling program (integer)

Output Parameters

dims	number of processes for each cartesian dimension (array of integer)
periods	periodicity (true/false) for each cartesian dimension (array of logical)
coords	coordinates of calling process in cartesian structure (array of integer)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_TOPOLOGY

Invalid topology. Either there is no topology associated with this communicator, or it is not the correct type (e.g., **MPI_CART** when expecting **MPI_GRAPH**).

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

`./src/topol/cart_get.c`

MPI_Cart_map

MPI_Cart_map

MPI_Cart_map — Maps process to Cartesian topology information

Synopsis

```
int MPI_Cart_map (
    MPI_Comm comm_old,
    int ndims,
    int *dims,
```

```
int *periods,
int *newrank)
```

Input Parameters

comm	input communicator (handle)
ndims	number of dimensions of Cartesian structure (integer)
dims	integer array of size ndims specifying the number of processes in each coordinate direction
periods	logical array of size ndims specifying the periodicity specification in each coordinate direction

Output Parameter

newrank	reordered rank of the calling process; MPI_UNDEFINED if calling process does not belong to grid (integer)
----------------	--

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_DIMS

Illegal dimension argument. A dimension argument is null or its length is less than or equal to zero.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

`./src/topol/cart_map.c`

MPI_Cart_rank

MPI_Cart_rank

MPI_Cart_rank — Determines process rank in communicator given Cartesian location

Synopsis

```
int MPI_Cart_rank (
    MPI_Comm comm,
    int *coords,
    int *rank )
```

Input Parameters

comm communicator with cartesian structure (handle)
coords integer array (of size **ndims**) specifying the cartesian coordinates of a process

Output Parameter

rank rank of specified process (integer)

Notes

Out-of-range coordinates are erroneous for non-periodic dimensions. Versions of MPICH before 1.2.2 returned **MPI_PROC_NULL** for the rank in this case.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_TOPOLOGY

Invalid topology. Either there is no topology associated with this communicator, or it is not the correct type (e.g., **MPI_CART** when expecting **MPI_GRAPH**).

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_SOURCE**.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

`./src/topol/cart_rank.c`

MPI_Cart_shift	MPI_Cart_shift
MPI_Cart_shift — Returns the shifted source and destination ranks, given a shift direction and amount	

Synopsis

```
int MPI_Cart_shift ( MPI_Comm comm, int direction, int displ,
                     int *source, int *dest )
```

Input Parameters

comm	communicator with cartesian structure (handle)
direction	coordinate dimension of shift (integer)
disp	displacement (> 0: upwards shift, < 0: downwards shift) (integer)

Output Parameters

rank_source	rank of source process (integer)
rank_dest	rank of destination process (integer)

Notes

The **direction** argument is in the range [0 ,n-1] for an n-dimensional Cartesian mesh.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_TOPOLOGY

Invalid topology. Either there is no topology associated with this communicator, or it is not the correct type (e.g., **MPI_CART** when expecting **MPI_GRAPH**).

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

```
./src/topol/cart_shift.c
```

MPI_Cart_sub**MPI_Cart_sub**

MPI_Cart_sub — Partitions a communicator into subgroups which form lower-dimensional cartesian subgrids

Synopsis

```
int MPI_Cart_sub ( MPI_Comm comm, int *remain_dims, MPI_Comm *comm_new )
```

Input Parameters

comm	communicator with cartesian structure (handle)
remain_dims	the <i>i</i> th entry of <i>remain_dims</i> specifies whether the <i>i</i> th dimension is kept in the subgrid (true) or is dropped (false) (logical vector)

Output Parameter

newcomm	communicator containing the subgrid that includes the calling process (handle)
----------------	--

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_TOPOLOGY

Invalid topology. Either there is no topology associated with this communicator, or it is not the correct type (e.g., **MPI_CART** when expecting **MPI_GRAPH**).

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call
(not even allowed in **MPI_Comm_rank**).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific
error class (e.g., **MPI_ERR_RANK**).

Location

`./src/topol/cart_sub.c`

MPI_Cartdim_get**MPI_Cartdim_get**

MPI_Cartdim_get — Retrieves Cartesian topology information associated with a communicator

Synopsis

```
int MPI_Cartdim_get ( MPI_Comm comm, int *ndims )
```

Input Parameter

comm communicator with cartesian structure (handle)

Output Parameter

ndims number of dimensions of the cartesian structure (integer)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call
(not even allowed in **MPI_Comm_rank**).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific
error class (e.g., **MPI_ERR_RANK**).

Location

`./src/topol/cartdim_get.c`

MPI_Comm_compare	MPI_Comm_compare
MPI_Comm_compare — Compares two communicators	

Synopsis

```
int MPI_Comm_compare (
    MPI_Comm comm1,
    MPI_Comm comm2,
    int *result)
```

Input Parameters

comm1	comm1 (handle)
comm2	comm2 (handle)

Output Parameter

result	integer which is MPI_IDENT if the contexts and groups are the same, MPI_CONGRUENT if different contexts but identical groups, MPI_SIMILAR if different contexts but similar groups, and MPI_UNEQUAL otherwise
---------------	---

Using '**MPI_COMM_NULL**' with '**MPI_Comm_compare**'

It is an error to use **MPI_COMM_NULL** as one of the arguments to **MPI_Comm_compare**. The relevant sections of the MPI standard are

- .(2.4.1 Opaque Objects)A null handle argument is an erroneous **IN** argument in MPI calls, unless an exception is explicitly stated in the text that defines the function.
- .(5.4.1. Communicator Accessors)<no text in **MPI_COMM_COMPARE** allowing a null handle>

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

`./src/context/commcompare.c`

MPI_Comm_create**MPI_Comm_create**

MPI_Comm_create — Creates a new communicator

Synopsis

```
int MPI_Comm_create ( MPI_Comm comm, MPI_Group group, MPI_Comm *comm_out )
```

Input Parameters

comm	communicator (handle)
group	group, which is a subset of the group of comm (handle)

Output Parameter

comm_out	new communicator (handle)
-----------------	---------------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_GROUP

Null group passed to function.

MPI_ERR_INTERN

This error is returned when some part of the MPICH implementation is unable to acquire memory.

See Also

`MPI_Comm_free`

Location

`./src/context/comm_create.c`

MPI_Comm_dup**MPI_Comm_dup**

MPI_Comm_dup — Duplicates an existing communicator with all its cached information

Synopsis

```
int MPI_Comm_dup (
    MPI_Comm comm,
    MPI_Comm *comm_out )
```

Input Parameter

comm communicator (handle)

Output Parameter

newcomm A new communicator over the same group as **comm** but with a new context. See notes. (handle)

Notes

This routine is used to create a new communicator that has a new communication context but contains the same group of processes as the input communicator. Since all MPI communication is performed within a communicator (specifies as the group of processes *plus* the context), this routine provides an effective way to create a private communicator for use by a software module or library. In particular, no library routine should use `MPI_COMM_WORLD` as the communicator; instead, a duplicate of a user-specified communicator should always be used. For more information, see *Using MPI*, 2nd edition.

Because this routine essentially produces a copy of a communicator, it also copies any attributes that have been defined on the input communicator, using the attribute copy function specified by the `copy_function` argument to `MPI_Keyval_create`. This is particularly useful for (a) attributes that describe some property of the group associated with the communicator, such as its interconnection topology and (b) communicators that are given back to the user; the attributes in this case can track subsequent `MPI_Comm_dup` operations on this communicator.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call
(not even allowed in `MPI_Comm_rank`).

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

See Also

`MPI_Comm_free`, `MPI_Keyval_create`, `MPI_Attr_set`, `MPI_Attr_delete`

Location

`./src/context/comm_dup.c`

`MPI_Comm_free`

`MPI_Comm_free`

`MPI_Comm_free` — Marks the communicator object for deallocation

Synopsis

```
int MPI_Comm_free ( MPI_Comm *commpp )
```

Input Parameter

`comm` communicator to be destroyed (handle)

Null Handles

The MPI 1.1 specification, in the section on opaque objects, explicitly

disallows freeing a null communicator. The text from the standard is

A null handle argument is an erroneous IN argument in MPI calls, unless an exception is explicitly stated in the text that defines the function. Such exception is allowed for handles to request objects in Wait and Test calls (sections Communication Completion and Multiple Completions). Otherwise, a null handle can only be passed to a function that allocates a new object and returns a reference to it in the handle.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

Location

`./src/context/comm_free.c`

`MPI_Comm_get_name`

`MPI_Comm_get_name`

`MPI_Comm_get_name` — return the print name from the communicator

Synopsis

```
int MPI_Comm_get_name( MPI_Comm comm, char *namep, int *reslen )
```

Input Parameter

<code>comm</code>	Communicator to get name of (handle)
-------------------	--------------------------------------

Output Parameters

namep	One output, contains the name of the communicator. It must be an array of size at least <code>MPI_MAX_NAME_STRING</code> .
reslen	Number of characters in name

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

Location

`./src/context/comm_name_get.c`

`MPI_Comm_group`

`MPI_Comm_group`

`MPI_Comm_group` — Accesses the group associated with given communicator

Synopsis

```
int MPI_Comm_group (
    MPI_Comm comm,
    MPI_Group *group )
```

Input Parameter

`comm` Communicator

Output Parameter

`group` Group in communicator

Using 'MPI_COMM_NULL' with 'MPI_Comm_group'

It is an error to use `MPI_COMM_NULL` as one of the arguments to `MPI_Comm_group`. The relevant sections of the MPI standard are

.(2.4.1 Opaque Objects)A null handle argument is an erroneous IN argument in MPI calls, unless an exception is explicitly stated in the text that defines the function.

.(5.3.2. Group Constructors)<no text in `MPI_COMM_GROUP` allowing a null handle>

Previous versions of MPICH allow `MPI_COMM_NULL` in this function. In the interests of promoting portability of applications, we have changed the behavior of `MPI_Comm_group` to detect this violation of the MPI standard.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

Location

`./src/context/comm_group.c`

`MPI_Comm_rank`

`MPI_Comm_rank`

`MPI_Comm_rank` — Determines the rank of the calling process in the communicator

Synopsis

```
int MPI_Comm_rank ( MPI_Comm comm, int *rank )
```

Input Parameters

`comm` communicator (handle)

Output Parameter

rank rank of the calling process in group of **comm** (integer)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

Location

`./src/context/comm_rank.c`

MPI_Comm_remote_group

MPI_Comm_remote_group

MPI_Comm_remote_group — Accesses the remote group associated with the given inter-communicator

Synopsis

```
int MPI_Comm_remote_group ( MPI_Comm comm, MPI_Group *group )
```

Input Parameter

comm Communicator (must be intercommunicator)

Output Parameter

group remote group of communicator

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

Location

`./src/context/comm_rgroup.c`

<code>MPI_Comm_remote_size</code>	<code>MPI_Comm_remote_size</code>
<code>MPI_Comm_remote_size</code> — Determines the size of the remote group associated with an inter-communicator	

Synopsis

```
int MPI_Comm_remote_size ( MPI_Comm comm, int *size )
```

Input Parameter

`comm` communicator (handle)

Output Parameter

`size` number of processes in the group of `comm` (integer)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

Location

`./src/context/comm_rsize.c`

`MPI_Comm_set_name`

`MPI_Comm_set_name`

`MPI_Comm_set_name` — give a print name to the communicator

Synopsis

```
int MPI_Comm_set_name( MPI_Comm com, char *name )
```

Input Parameters

<code>com</code>	Communicator to name (handle)
<code>name</code>	Name for communicator

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

Location

`./src/context/comm_name_put.c`

MPI_Comm_size

MPI_Comm_size

MPI_Comm_size — Determines the size of the group associated with a communicator

Synopsis

```
int MPI_Comm_size ( MPI_Comm comm, int *size )
```

Input Parameter

comm communicator (handle)

Output Parameter

size number of processes in the group of **comm** (integer)

Notes

MPI_COMM_NULL is *not* considered a valid argument to this function.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

Location

```
./src/context/comm_size.c
```

MPI_Comm_split**MPI_Comm_split**

MPI_Comm_split — Creates new communicators based on colors and keys

Synopsis

```
int MPI_Comm_split ( MPI_Comm comm, int color, int key, MPI_Comm *comm_out )
```

Input Parameters

comm	communicator (handle)
color	control of subset assignment (nonnegative integer). Processes with the same color are in the same new communicator
key	control of rank assignment (integer)

Output Parameter

newcomm	new communicator (handle)
----------------	---------------------------

Notes

The `color` must be non-negative or `MPI_UNDEFINED`.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Algorithm

The current algorithm used has quite a few (read: a lot of) inefficiencies that can be removed. Here is what we do for now

- 1) A table is built of colors, and keys (has a next field also).
- 2) The tables of all processes are merged using {\tt MPI_Allreduce}.
- 3) Two contexts are allocated for all the comms to be created. These same two contexts can be used for all created communicators since the communicators will not overlap.
- 4) If the local process has a color of {\tt MPI_UNDEFINED}, it can return

```

    a {\tt NULL} comm.
5) The table entries that match the local process color are sorted
   by key/rank.
6) A group is created from the sorted list and a communicator is created
   with this group and the previously allocated contexts.

```

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

See Also

`MPI_Comm_free`

Location

`./src/context/comm_split.c`

`MPI_Comm_test_inter`

`MPI_Comm_test_inter`

`MPI_Comm_test_inter` — Tests to see if a comm is an inter-communicator

Synopsis

```
int MPI_Comm_test_inter ( MPI_Comm comm, int *flag )
```

Input Parameter

`comm` communicator (handle)

Output Parameter

`flag` (logical)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call
(not even allowed in `MPI_Comm_rank`).

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific
error class (e.g., `MPI_ERR_RANK`).

Location

`./src/context/comm_testic.c`

`MPI_DUP_FN`

`MPI_DUP_FN`

`MPI_DUP_FN` — A function to simple-mindedly copy attributes

Location

`./src/context/dup_fn.c`

`MPI_Dims_create`

`MPI_Dims_create`

`MPI_Dims_create` — Creates a division of processors in a cartesian grid

Synopsis

```
int MPI_Dims_create(
    int nnodes,
    int ndims,
    int *dims)
```

Input Parameters

nnodes	number of nodes in a grid (integer)
ndims	number of cartesian dimensions (integer)

In/Out Parameter

dims	integer array of size ndims specifying the number of nodes in each dimension
-------------	---

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./src/topol/dims_create.c`

MPI_Errhandler_create

MPI_Errhandler_create

MPI_Errhandler_create — Creates an MPI-style errorhandler

Synopsis

```
int MPI_Errhandler_create(
    MPI_Handler_function *function,
    MPI_Errhandler      *errhandler)
```

Input Parameter

function	user defined error handling procedure
-----------------	---------------------------------------

Output Parameter

errhandler	MPI error handler (handle)
-------------------	----------------------------

Notes

The MPI Standard states that an implementation may make the output value (**errhandler**) simply the address of the function. However, the action of **MPI_Errhandler_free** makes this impossible, since it is required to set the value of the argument to **MPI_ERRHANDLER_NULL**. In addition, the actual error handler must remain until all communicators that use it are freed.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

Location

```
./src/env/errcreate.c
```

`MPI_Errhandler_free`

`MPI_Errhandler_free`

`MPI_Errhandler_free` — Frees an MPI-style errorhandler

Synopsis

```
int MPI_Errhandler_free( MPI_Errhandler *errhandler )
```

Input Parameter

`errhandler` MPI error handler (handle). Set to `MPI_ERRHANDLER_NULL` on exit.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current

MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

`./src/env/errfree.c`

MPI_Errhandler_get

MPI_Errhandler_get

MPI_Errhandler_get — Gets the error handler for a communicator

Synopsis

```
int MPI_Errhandler_get( MPI_Comm comm, MPI_Errhandler *errhandler )
```

Input Parameter

comm communicator to get the error handler from (handle)

Output Parameter

errhandler MPI error handler currently associated with communicator (handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Note on Implementation

The MPI Standard was unclear on whether this routine required the user to call **MPI_Errhandler_free** once for each call made to this routine in order to free the error handler. After some debate, the MPI Forum added an explicit statement that users are required to call **MPI_Errhandler_free** when the return value from this routine is no longer needed. This behavior is similar to the other MPI routines for getting objects; for example, **MPI_Comm_group** requires that the user call **MPI_Group_free** when the group returned by **MPI_Comm_group** is no longer needed.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

Location

`./src/env/errget.c`

`MPI_Errhandler_set`

`MPI_Errhandler_set`

`MPI_Errhandler_set` — Sets the error handler for a communicator

Synopsis

```
int MPI_Errhandler_set( MPI_Comm comm, MPI_Errhandler errhandler )
```

Input Parameters

<code>comm</code>	communicator to set the error handler for (handle)
<code>errhandler</code>	new MPI error handler for communicator (handle)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call
(not even allowed in **MPI_Comm_rank**).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific
error class (e.g., **MPI_ERR_RANK**).

Location

`./src/env/errset.c`

MPI_Error_class	MPI_Error_class
------------------------	------------------------

MPI_Error_class — Converts an error code into an error class

Synopsis

```
int MPI_Error_class(
    int errorcode,
    int *errorclass)
```

Input Parameter

errorcode Error code returned by an MPI routine

Output Parameter

errorclass Error class associated with **errorcode**

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./src/env/errclass.c`

MPI_Error_string	MPI_Error_string
-------------------------	-------------------------

MPI_Error_string — Return a string for a given error code

Synopsis

```
int MPI_Error_string( int errorcode, char *string, int *resultlen )
```

Input Parameters

errorcode Error code returned by an MPI routine or an MPI error class

Output Parameter

string Text that corresponds to the errorcode

resultlen Length of string

Notes: Error codes are the values return by MPI routines (in C) or in the **ierr** argument (in Fortran). These can be converted into error classes with the routine **MPI_Error_class**.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./src/env/errorstring.c`

MPI_File_c2f

MPI_File_c2f

MPI_File_c2f— Translates a C file handle to a Fortran file handle

Synopsis

```
MPI_Fint MPI_File_c2f(MPI_File fh)
```

Input Parameters

fh C file handle (handle)

Return Value

Fortran file handle (integer)

Location

```
./romio/mpi-io/file_c2f.c
```

MPI_File_close		MPI_File_close
-----------------------	--	-----------------------

MPI_File_close — Closes a file

Synopsis

```
int MPI_File_close(MPI_File *fh)
```

Input Parameters

fh file handle (handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./romio/mpi-io/close.c
```

MPI_File_delete		MPI_File_delete
------------------------	--	------------------------

MPI_File_delete — Deletes a file

Synopsis

```
int MPI_File_delete(char *filename, MPI_Info info)
```

Input Parameters

filename name of file to delete (string)
info info object (handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./romio/mpi-io/delete.c
```

MPI_File_f2c**MPI_File_f2c****MPI_File_f2c** — Translates a Fortran file handle to a C file handle**Synopsis**

```
MPI_File MPI_File_f2c(MPI_Fint fh)
```

Input Parameters

fh Fortran file handle (integer)

Return Value

C file handle (handle)

Location

```
./romio/mpi-io/file_f2c.c
```

MPI_File_get_amode**MPI_File_get_amode****MPI_File_get_amode** — Returns the file access mode**Synopsis**

```
int MPI_File_get_amode(MPI_File fh, int *amode)
```

Input Parameters

fh file handle (handle)

Output Parameters

amode access mode (integer)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./romio/mpi-io/get_amode.c
```

MPI_File_get_atomicity	MPI_File_get_atomicity
-------------------------------	-------------------------------

MPI_File_get_atomicity — Returns the atomicity mode

Synopsis

```
int MPI_File_get_atomicity(MPI_File fh, int *flag)
```

Input Parameters

fh file handle (handle)

Output Parameters

flag true if atomic mode, false if nonatomic mode (logical)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./romio/mpi-io/get_atom.c
```

MPI_File_get_byte_offset	MPI_File_get_byte_offset
---------------------------------	---------------------------------

MPI_File_get_byte_offset — Returns the absolute byte position in the file corresponding to "offset" etypes relative to the current view

Synopsis

```
int MPI_File_get_byte_offset(MPI_File fh, MPI_Offset offset, MPI_Offset *disp)
```

Input Parameters

fh	file handle (handle)
offset	offset (nonnegative integer)

Output Parameters

disp absolute byte position of offset (nonnegative integer)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./romio/mpi-io/get_bytoff.c`

MPI_File_get_errhandler

MPI_File_get_errhandler

MPI_File_get_errhandler — Returns the error handler for a file

Synopsis

```
int MPI_File_get_errhandler(MPI_File fh, MPI_Errhandler *errhandler)
```

Input Parameters

fh file handle (handle)

Output Parameters

errhandler error handler (handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./romio/mpi-io/get_errh.c`

MPI_File_get_group

MPI_File_get_group

MPI_File_get_group — Returns the group of processes that opened the file

Synopsis

```
int MPI_File_get_group(MPI_File fh, MPI_Group *group)
```

Input Parameters

fh file handle (handle)

Output Parameters

group group that opened the file (handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./romio/mpi-io/get_group.c`

MPI_File_get_info

MPI_File_get_info

MPI_File_get_info — Returns the hints for a file that are actually being used by MPI

Synopsis

```
int MPI_File_get_info(MPI_File fh, MPI_Info *info_used)
```

Input Parameters

fh file handle (handle)

Output Parameters

info_used info object (handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./romio/mpi-io/get_info.c
```

MPI_File_get_position	MPI_File_get_position
------------------------------	------------------------------

MPI_File_get_position — Returns the current position of the individual file pointer in etype units relative to the current view

Synopsis

```
int MPI_File_get_position(MPI_File fh, MPI_Offset *offset)
```

Input Parameters

fh file handle (handle)

Output Parameters

offset offset of individual file pointer (nonnegative integer)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./romio/mpi-io/get_posn.c
```

MPI_File_get_position_shared	MPI_File_get_position_shared
-------------------------------------	-------------------------------------

MPI_File_get_position_shared — Returns the current position of the shared file pointer in etype units relative to the current view

Synopsis

```
int MPI_File_get_position_shared(MPI_File fh, MPI_Offset *offset)
```

Input Parameters

fh file handle (handle)

Output Parameters

offset offset of shared file pointer (nonnegative integer)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./romio/mpi-io/get_posn_sh.c`

MPI_File_get_size	MPI_File_get_size
--------------------------	--------------------------

MPI_File_get_size — Returns the file size

Synopsis

```
int MPI_File_get_size(MPI_File fh, MPI_Offset *size)
```

Input Parameters

fh file handle (handle)

Output Parameters

size size of the file in bytes (nonnegative integer)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./romio/mpi-io/get_size.c`

MPI_File_get_type_extent	MPI_File_get_type_extent
---------------------------------	---------------------------------

MPI_File_get_type_extent — Returns the extent of datatype in the file

Synopsis

```
int MPI_File_get_type_extent(MPI_File fh, MPI_Datatype datatype,
                           MPI_Aint *extent)
```

Input Parameters

fh	file handle (handle)
datatype	datatype (handle)

Output Parameters

extent	extent of the datatype (nonnegative integer)
---------------	--

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./romio/mpi-io/get_extent.c`

MPI_File_get_view

MPI_File_get_view

MPI_File_get_view — Returns the file view

Synopsis

```
int MPI_File_get_view(MPI_File fh, MPI_Offset *disp, MPI_Datatype *etype,
                      MPI_Datatype *filetype, char *datarep)
```

Input Parameters

fh	file handle (handle)
-----------	----------------------

Output Parameters

disp	displacement (nonnegative integer)
etype	elementary datatype (handle)
filetype	filetype (handle)
datarep	data representation (string)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./romio/mpi-io/get_view.c
```

<code>MPI_File_iread</code>	<code>MPI_File_iread</code>
-----------------------------	-----------------------------

`MPI_File_iread` — Nonblocking read using individual file pointer

Synopsis

```
int MPI_File_iread(MPI_File fh, void *buf, int count,
                    MPI_Datatype datatype, MPIIO_Request *request)
```

Input Parameters

<code>fh</code>	file handle (handle)
<code>count</code>	number of elements in buffer (nonnegative integer)
<code>datatype</code>	datatype of each buffer element (handle)

Output Parameters

<code>buf</code>	initial address of buffer (choice)
<code>request</code>	request object (handle)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./romio/mpi-io/iread.c
```

<code>MPI_File_iread_at</code>	<code>MPI_File_iread_at</code>
--------------------------------	--------------------------------

`MPI_File_iread_at` — Nonblocking read using explicit offset

Synopsis

```
int MPI_File_iread_at(MPI_File fh, MPI_Offset offset, void *buf,
                      int count, MPI_Datatype datatype,
                      MPIO_Request *request)
```

Input Parameters

fh	file handle (handle)
offset	file offset (nonnegative integer)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

buf	initial address of buffer (choice)
request	request object (handle)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./romio/mpi-io/iread_at.c`

MPI_File_iread_shared

MPI_File_iread_shared

MPI_File_iread_shared — Nonblocking read using shared file pointer

Synopsis

```
int MPI_File_iread_shared(MPI_File fh, void *buf, int count,
                           MPI_Datatype datatype, MPIO_Request *request)
```

Input Parameters

fh	file handle (handle)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

buf	initial address of buffer (choice)
request	request object (handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./romio/mpi-io/iread_sh.c
```

MPI_File_iwrite

MPI_File_iwrite

MPI_File_iwrite — Nonblocking write using individual file pointer

Synopsis

```
int MPI_File_iwrite(MPI_File fh, void *buf, int count,
                    MPI_Datatype datatype, MPIIO_Request *request)
```

Input Parameters

fh	file handle (handle)
buf	initial address of buffer (choice)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

request	request object (handle)
----------------	-------------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./romio/mpi-io/iwrite.c
```

MPI_File_iwrite_at **MPI_File_iwrite_at**

MPI_File_iwrite_at — Nonblocking write using explicit offset**Synopsis**

```
int MPI_File_iwrite_at(MPI_File fh, MPI_Offset offset, void *buf,
                      int count, MPI_Datatype datatype,
                      MPIO_Request *request)
```

Input Parameters

fh	file handle (handle)
offset	file offset (nonnegative integer)
buf	initial address of buffer (choice)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

request	request object (handle)
----------------	-------------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./romio/mpi-io/iwrite_at.c
```

MPI_File_iwrite_shared **MPI_File_iwrite_shared**

MPI_File_iwrite_shared — Nonblocking write using shared file pointer**Synopsis**

```
int MPI_File_iwrite_shared(MPI_File fh, void *buf, int count,
                           MPI_Datatype datatype, MPIO_Request *request)
```

Input Parameters

fh	file handle (handle)
buf	initial address of buffer (choice)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

request	request object (handle)
----------------	-------------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./romio/mpi-io/iwrite_sh.c`

MPI_File_open

MPI_File_open

MPI_File_open — Opens a file

Synopsis

```
int MPI_File_open(MPI_Comm comm, char *filename, int amode,
                  MPI_Info info, MPI_File *fh)
```

Input Parameters

comm	communicator (handle)
filename	name of file to open (string)
amode	file access mode (integer)
info	info object (handle)

Output Parameters

fh	file handle (handle)
-----------	----------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./romio/mpi-io/open.c`

MPI_File_preallocate

MPI_File_preallocate

MPI_File_preallocate — Preallocates storage space for a file

Synopsis

```
int MPI_File_preallocate(MPI_File fh, MPI_Offset size)
```

Input Parameters

fh	file handle (handle)
size	size to preallocate (nonnegative integer)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./romio/mpi-io/prealloc.c`

MPI_File_read

MPI_File_read

MPI_File_read — Read using individual file pointer

Synopsis

```
int MPI_File_read(MPI_File fh, void *buf, int count,
                  MPI_Datatype datatype, MPI_Status *status)
```

Input Parameters

fh	file handle (handle)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

buf	initial address of buffer (choice)
status	status object (Status)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./romio/mpi-io/read.c`

MPI_File_read_all

MPI_File_read_all

MPI_File_read_all — Collective read using individual file pointer

Synopsis

```
int MPI_File_read_all(MPI_File fh, void *buf, int count,
                      MPI_Datatype datatype, MPI_Status *status)
```

Input Parameters

fh	file handle (handle)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

buf	initial address of buffer (choice)
status	status object (Status)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./romio/mpi-io/read_all.c`

MPI_File_read_all_begin**MPI_File_read_all_begin**

MPI_File_read_all_begin — Begin a split collective read using individual file pointer

Synopsis

```
int MPI_File_read_all_begin(MPI_File fh, void *buf, int count,
                           MPI_Datatype datatype)
```

Input Parameters

fh	file handle (handle)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

buf	initial address of buffer (choice)
------------	------------------------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./romio/mpi-io/read_allb.c`

MPI_File_read_all_end**MPI_File_read_all_end**

MPI_File_read_all_end — Complete a split collective read using individual file pointer

Synopsis

```
int MPI_File_read_all_end(MPI_File fh, void *buf, MPI_Status *status)
```

Input Parameters

fh	file handle (handle)
-----------	----------------------

Output Parameters

buf	initial address of buffer (choice)
status	status object (Status)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./romio/mpi-io/read_all.c
```

<code>MPI_File_read_at</code>	<code>MPI_File_read_at</code>
-------------------------------	-------------------------------

`MPI_File_read_at` — Read using explicit offset

Synopsis

```
int MPI_File_read_at(MPI_File fh, MPI_Offset offset, void *buf,
                     int count, MPI_Datatype datatype, MPI_Status *status)
```

Input Parameters

<code>fh</code>	file handle (handle)
<code>offset</code>	file offset (nonnegative integer)
<code>count</code>	number of elements in buffer (nonnegative integer)
<code>datatype</code>	datatype of each buffer element (handle)

Output Parameters

<code>buf</code>	initial address of buffer (choice)
<code>status</code>	status object (Status)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./romio/mpi-io/read_at_all.c
```

<code>MPI_File_read_at_all</code>	<code>MPI_File_read_at_all</code>
-----------------------------------	-----------------------------------

`MPI_File_read_at_all` — Collective read using explicit offset

Synopsis

```
int MPI_File_read_at_all(MPI_File fh, MPI_Offset offset, void *buf,
                        int count, MPI_Datatype datatype,
                        MPI_Status *status)
```

Input Parameters

fh	file handle (handle)
offset	file offset (nonnegative integer)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

buf	initial address of buffer (choice)
status	status object (Status)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./romio/mpi-io/read_atall.c`

MPI_File_read_at_all_begin

MPI_File_read_at_all_begin

MPI_File_read_at_all_begin — Begin a split collective read using explicit offset

Synopsis

```
int MPI_File_read_at_all_begin(MPI_File fh, MPI_Offset offset, void *buf,
                               int count, MPI_Datatype datatype)
```

Input Parameters

fh	file handle (handle)
offset	file offset (nonnegative integer)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

buf initial address of buffer (choice)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./romio/mpi-io/rd_atallb.c`

MPI_File_read_at_all_end

MPI_File_read_at_all_end

MPI_File_read_at_all_end — Complete a split collective read using explicit offset

Synopsis

```
int MPI_File_read_at_all_end(MPI_File fh, void *buf, MPI_Status *status)
```

Input Parameters

fh file handle (handle)

Output Parameters

buf initial address of buffer (choice)

status status object (Status)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./romio/mpi-io/rd_atalle.c`

MPI_File_read_ordered

MPI_File_read_ordered

MPI_File_read_ordered — Collective read using shared file pointer

Synopsis

```
int MPI_File_read_ordered(MPI_File fh, void *buf, int count,
                           MPI_Datatype datatype, MPI_Status *status)
```

Input Parameters

fh	file handle (handle)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

buf	initial address of buffer (choice)
status	status object (Status)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./romio/mpi-io/read_ord.c`

MPI_File_read_ordered_begin

MPI_File_read_ordered_begin

MPI_File_read_ordered_begin — Begin a split collective read using shared file pointer

Synopsis

```
int MPI_File_read_ordered_begin(MPI_File fh, void *buf, int count,
                                MPI_Datatype datatype)
```

Input Parameters

fh	file handle (handle)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

buf	initial address of buffer (choice)
------------	------------------------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./romio/mpi-io/read_ordb.c
```

<code>MPI_File_read_ordered_end</code>	<code>MPI_File_read_ordered_end</code>
--	--

`MPI_File_read_ordered_end` — Complete a split collective read using shared file pointer

Synopsis

```
int MPI_File_read_ordered_end(MPI_File fh, void *buf, MPI_Status *status)
```

Input Parameters

fh file handle (handle)

Output Parameters

buf	initial address of buffer (choice)
status	status object (Status)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./romio/mpi-io/read_orde.c
```

<code>MPI_File_read_shared</code>	<code>MPI_File_read_shared</code>
-----------------------------------	-----------------------------------

`MPI_File_read_shared` — Read using shared file pointer

Synopsis

```
int MPI_File_read_shared(MPI_File fh, void *buf, int count,
                         MPI_Datatype datatype, MPI_Status *status)
```

Input Parameters

fh	file handle (handle)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

buf	initial address of buffer (choice)
status	status object (Status)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./romio/mpi-io/read_sh.c`

MPI_File_seek

MPI_File_seek

MPI_File_seek — Updates the individual file pointer

Synopsis

```
int MPI_File_seek(MPI_File fh, MPI_Offset offset, int whence)
```

Input Parameters

fh	file handle (handle)
offset	file offset (integer)
whence	update mode (state)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./romio/mpi-io/seek.c
```

MPI_File_seek_shared

MPI_File_seek_shared

MPI_File_seek_shared — Updates the shared file pointer

Synopsis

```
int MPI_File_seek_shared(MPI_File fh, MPI_Offset offset, int whence)
```

Input Parameters

fh	file handle (handle)
offset	file offset (integer)
whence	update mode (state)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./romio/mpi-io/seek_sh.c
```

MPI_File_set_atomicity

MPI_File_set_atomicity

MPI_File_set_atomicity — Sets the atomicity mode

Synopsis

```
int MPI_File_set_atomicity(MPI_File fh, int flag)
```

Input Parameters

fh	file handle (handle)
flag	true to set atomic mode, false to set nonatomic mode (logical)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./romio/mpi-io/set_atom.c
```

`MPI_File_set_errhandler`

`MPI_File_set_errhandler`

`MPI_File_set_errhandler` — Sets the error handler for a file

Synopsis

```
int MPI_File_set_errhandler(MPI_File fh, MPI_Errhandler errhandler)
```

Input Parameters

<code>fh</code>	file handle (handle)
<code>errhandler</code>	error handler (handle)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./romio/mpi-io/set_errh.c
```

`MPI_File_set_info`

`MPI_File_set_info`

`MPI_File_set_info` — Sets new values for the hints associated with a file

Synopsis

```
int MPI_File_set_info(MPI_File fh, MPI_Info info)
```

Input Parameters

fh	file handle (handle)
info	info object (handle)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./romio/mpi-io/set_info.c
```

`MPI_File_set_size`

`MPI_File_set_size`

`MPI_File_set_size` — Sets the file size

Synopsis

```
int MPI_File_set_size(MPI_File fh, MPI_Offset size)
```

Input Parameters

fh	file handle (handle)
size	size to truncate or expand file (nonnegative integer)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./romio/mpi-io/set_size.c
```

`MPI_File_set_view`

`MPI_File_set_view`

`MPI_File_set_view` — Sets the file view

Synopsis

```
int MPI_File_set_view(MPI_File fh, MPI_Offset disp, MPI_Datatype etype,
                      MPI_Datatype filetype, char *datarep, MPI_Info info)
```

Input Parameters

fh	file handle (handle)
disp	displacement (nonnegative integer)
etype	elementary datatype (handle)
filetype	filetype (handle)
datarep	data representation (string)
info	info object (handle)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./romio/mpi-io/set_view.c`

MPI_File_sync

MPI_File_sync

MPI_File_sync — Causes all previous writes to be transferred to the storage device

Synopsis

```
int MPI_File_sync(MPI_File fh)
```

Input Parameters

fh	file handle (handle)
-----------	----------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./romio/mpi-io/fsync.c`

MPI_File_write

MPI_File_write

MPI_File_write — Write using individual file pointer

Synopsis

```
int MPI_File_write(MPI_File fh, void *buf, int count,
                   MPI_Datatype datatype, MPI_Status *status)
```

Input Parameters

fh	file handle (handle)
buf	initial address of buffer (choice)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

status	status object (Status)
---------------	------------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./romio/mpi-io/write.c`

MPI_File_write_all

MPI_File_write_all

MPI_File_write_all — Collective write using individual file pointer

Synopsis

```
int MPI_File_write_all(MPI_File fh, void *buf, int count,
                      MPI_Datatype datatype, MPI_Status *status)
```

Input Parameters

fh	file handle (handle)
buf	initial address of buffer (choice)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

status	status object (Status)
---------------	------------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./romio/mpi-io/write_all.c`

MPI_File_write_all_begin

MPI_File_write_all_begin

MPI_File_write_all_begin — Begin a split collective write using individual file pointer

Synopsis

```
int MPI_File_write_all_begin(MPI_File fh, void *buf, int count,
                           MPI_Datatype datatype)
```

Input Parameters

fh	file handle (handle)
buf	initial address of buffer (choice)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./romio/mpi-io/write_allb.c`

MPI_File_write_all_end	MPI_File_write_all_end
-------------------------------	-------------------------------

MPI_File_write_all_end — Complete a split collective write using individual file pointer

Synopsis

```
int MPI_File_write_all_end(MPI_File fh, void *buf, MPI_Status *status)
```

Input Parameters

fh file handle (handle)

Output Parameters

buf	initial address of buffer (choice)
status	status object (Status)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./romio/mpi-io/write_allc.c`

MPI_File_write_at	MPI_File_write_at
--------------------------	--------------------------

MPI_File_write_at — Write using explicit offset

Synopsis

```
int MPI_File_write_at(MPI_File fh, MPI_Offset offset, void *buf,
                      int count, MPI_Datatype datatype,
                      MPI_Status *status)
```

Input Parameters

fh	file handle (handle)
offset	file offset (nonnegative integer)
buf	initial address of buffer (choice)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

status	status object (Status)
---------------	------------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./romio/mpi-io/write_at.c`

MPI_File_write_at_all

MPI_File_write_at_all

MPI_File_write_at_all—Collective write using explicit offset

Synopsis

```
int MPI_File_write_at_all(MPI_File fh, MPI_Offset offset, void *buf,
                           int count, MPI_Datatype datatype,
                           MPI_Status *status)
```

Input Parameters

fh	file handle (handle)
offset	file offset (nonnegative integer)
buf	initial address of buffer (choice)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

status	status object (Status)
---------------	------------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./romio/mpi-io/write_atall.c
```

<code>MPI_File_write_at_all_begin</code>	<code>MPI_File_write_at_all_begin</code>
--	--

`MPI_File_write_at_all_begin` — Begin a split collective write using explicit offset

Synopsis

```
int MPI_File_write_at_all_begin(MPI_File fh, MPI_Offset offset, void *buf,
                                int count, MPI_Datatype datatype)
```

Input Parameters

<code>fh</code>	file handle (handle)
<code>offset</code>	file offset (nonnegative integer)
<code>buf</code>	initial address of buffer (choice)
<code>count</code>	number of elements in buffer (nonnegative integer)
<code>datatype</code>	datatype of each buffer element (handle)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./romio/mpi-io/wr_atallb.c
```

<code>MPI_File_write_at_all_end</code>	<code>MPI_File_write_at_all_end</code>
--	--

`MPI_File_write_at_all_end` — Complete a split collective write using explicit offset

Synopsis

```
int MPI_File_write_at_all_end(MPI_File fh, void *buf, MPI_Status *status)
```

Input Parameters

fh	file handle (handle)
buf	initial address of buffer (choice)

Output Parameters

status	status object (Status)
---------------	------------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./romio/mpi-io/wr_atalle.c`

MPI_File_write_ordered

MPI_File_write_ordered

MPI_File_write_ordered — Collective write using shared file pointer

Synopsis

```
int MPI_File_write_ordered(MPI_File fh, void *buf, int count,
                           MPI_Datatype datatype, MPI_Status *status)
```

Input Parameters

fh	file handle (handle)
buf	initial address of buffer (choice)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

status	status object (Status)
---------------	------------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./romio/mpi-io/write_ord.c
```

MPI_File_write_ordered_begin	MPI_File_write_ordered_begin
-------------------------------------	-------------------------------------

MPI_File_write_ordered_begin — Begin a split collective write using shared file pointer

Synopsis

```
int MPI_File_write_ordered_begin(MPI_File fh, void *buf, int count,
                                 MPI_Datatype datatype)
```

Input Parameters

fh	file handle (handle)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

buf	initial address of buffer (choice)
------------	------------------------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./romio/mpi-io/write_ordb.c
```

MPI_File_write_ordered_end	MPI_File_write_ordered_end
-----------------------------------	-----------------------------------

MPI_File_write_ordered_end — Complete a split collective write using shared file pointer

Synopsis

```
int MPI_File_write_ordered_end(MPI_File fh, void *buf, MPI_Status *status)
```

Input Parameters

fh	file handle (handle)
-----------	----------------------

Output Parameters

buf	initial address of buffer (choice)
status	status object (Status)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./romio/mpi-io/write_ord.c
```

MPI_File_write_shared

MPI_File_write_shared

MPI_File_write_shared — Write using shared file pointer

Synopsis

```
int MPI_File_write_shared(MPI_File fh, void *buf, int count,
                           MPI_Datatype datatype, MPI_Status *status)
```

Input Parameters

fh	file handle (handle)
buf	initial address of buffer (choice)
count	number of elements in buffer (nonnegative integer)
datatype	datatype of each buffer element (handle)

Output Parameters

status	status object (Status)
---------------	------------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./romio/mpi-io/write_sh.c
```

MPI_Finalize**MPI_Finalize**

MPI_Finalize — Terminates MPI execution environment

Synopsis

```
int MPI_Finalize()
```

Notes

All processes must call this routine before exiting. The number of processes running *after* this routine is called is undefined; it is best not to perform much more than a `return rc` after calling `MPI_Finalize`.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./src/env/finalize.c
```

MPI_Finalized**MPI_Finalized**

MPI_Finalized — Indicates whether `MPI_Finalize` has been called.

Synopsis

```
int MPI_Finalized( int *flag )
```

Output Parameter

`flag` Flag is true if `MPI_Finalize` has been called and false otherwise.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./src/misc2/finalized.c`

MPI_Gather

MPI_Gather

MPI_Gather — Gathers together values from a group of processes

Synopsis

```
int MPI_Gather ( void *sendbuf, int sendcnt, MPI_Datatype sendtype,
                 void *recvbuf, int recvcount, MPI_Datatype recvtype,
                 int root, MPI_Comm comm )
```

Input Parameters

sendbuf	starting address of send buffer (choice)
sendcount	number of elements in send buffer (integer)
sendtype	data type of send buffer elements (handle)
recvcount	number of elements for any single receive (integer, significant only at root)
recvtype	data type of recv buffer elements (significant only at root) (handle)
root	rank of receiving process (integer)
comm	communicator (handle)

Output Parameter

recvbuf	address of receive buffer (choice, significant only at root)
----------------	--

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

MPI_ERR_BUFFER

Invalid buffer pointer. Usually a null buffer where one is not valid.

Location

`./src/coll/gather.c`

MPI_Gatherv**MPI_Gatherv**

MPI_Gatherv — Gathers into specified locations from all processes in a group

Synopsis

```
int MPI_Gatherv ( void *sendbuf, int sendcnt, MPI_Datatype sendtype,
                  void *recvbuf, int *recvcounts, int *displs,
                  MPI_Datatype recvtype,
                  int root, MPI_Comm comm )
```

Input Parameters

sendbuf	starting address of send buffer (choice)
sendcount	number of elements in send buffer (integer)
sendtype	data type of send buffer elements (handle)
recvcounts	integer array (of length group size) containing the number of elements that are received from each process (significant only at <code>root</code>)
displs	integer array (of length group size). Entry <code>i</code> specifies the displacement relative to <code>recvbuf</code> at which to place the incoming data from process <code>i</code> (significant only at <code>root</code>)
recvtype	data type of recv buffer elements (significant only at <code>root</code>) (handle)
root	rank of receiving process (integer)
comm	communicator (handle)

Output Parameter

recvbuf	address of receive buffer (choice, significant only at <code>root</code>)
----------------	--

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

`MPI_ERR_BUFFER`

Invalid buffer pointer. Usually a null buffer where one is not valid.

Location

`./src/coll/gatherv.c`

`MPI_Get_count`

`MPI_Get_count`

`MPI_Get_count` — Gets the number of "top level" elements

Synopsis

```
int MPI_Get_count(
    MPI_Status *status,
    MPI_Datatype datatype,
    int *count )
```

Input Parameters

<code>status</code>	return status of receive operation (Status)
<code>datatype</code>	datatype of each receive buffer element (handle)

Output Parameter

<code>count</code>	number of received elements (integer) Notes: If the size of the datatype is zero, this routine will return a count of zero. If the amount of data in <code>status</code> is not an exact multiple of the size of <code>datatype</code> (so that <code>count</code> would not be integral), a <code>count</code> of <code>MPI_UNDEFINED</code> is returned instead.
--------------------	--

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return

value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted `MPI_Datatype` (see `MPI_Type_commit`).

Location

`./src/pt2pt/getcount.c`

`MPI_Get_elements`

`MPI_Get_elements`

`MPI_Get_elements` — Returns the number of basic elements in a datatype

Synopsis

```
int MPI_Get_elements ( MPI_Status *status, MPI_Datatype datatype,
                      int *elements )
```

Input Parameters

<code>status</code>	return status of receive operation (Status)
<code>datatype</code>	datatype used by receive operation (handle)

Output Parameter

<code>count</code>	number of received basic elements (integer)
--------------------	---

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

Location

`./src/pt2pt/getelements.c`

`MPI_Get_processor_name`

`MPI_Get_processor_name`

`MPI_Get_processor_name` — Gets the name of the processor

Synopsis

```
int MPI_Get_processor_name(
    char *name,
    int *resultlen)
```

Output Parameters

<code>name</code>	A unique specifier for the actual (as opposed to virtual) node. This must be an array of size at least <code>MPI_MAX_PROCESSOR_NAME</code> .
<code>resultlen</code>	Length (in characters) of the name

Notes

The name returned should identify a particular piece of hardware; the exact format is implementation defined. This name may or may not be the same as might be returned by `gethostname`, `uname`, or `sysinfo`.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./src/env/getpname.c
```

MPI_Get_version — Gets the version of MPI

Synopsis

```
int MPI_Get_version( int *version, int *subversion )
```

Output Parameters

version Major version of MPI (1 or 2)
subversion Minor version of MPI.

Notes

The defined values `MPI_VERSION` and `MPI_SUBVERSION` contain the same information. This routine allows you to check that the library matches the version specified in the `mpi.h` and `mpif.h` files.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./src/env/getversion.c
```

MPI_Graph_create	MPI_Graph_create
<p>MPI_Graph_create — Makes a new communicator to which topology information has been attached</p>	

Synopsis

Input Parameters

comm_old	input communicator without topology (handle)
nnodes	number of nodes in graph (integer)
index	array of integers describing node degrees (see below)
edges	array of integers describing graph edges (see below)
reorder	ranking may be reordered (true) or not (false) (logical)

Output Parameter

comm_graph	communicator with graph topology added (handle)
-------------------	---

Algorithm

We ignore the **reorder** info currently.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_TOPOLOGY

Invalid topology. Either there is no topology associated with this communicator, or it is not the correct type (e.g., **MPI_CART** when expecting **MPI_GRAPH**).

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

`./src/topol/graphcreate.c`

MPI_Graph_get

MPI_Graph_get

MPI_Graph_get — Retrieves graph topology information associated with a communicator

Synopsis

```
int MPI_Graph_get ( MPI_Comm comm, int maxindex, int maxedges,
                    int *index, int *edges )
```

Input Parameters

comm	communicator with graph structure (handle)
maxindex	length of vector index in the calling program (integer)
maxedges	length of vector edges in the calling program (integer)

Output Parameter

index	array of integers containing the graph structure (for details see the definition of MPI_GRAPH_CREATE)
edges	array of integers containing the graph structure

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_TOPOLOGY

Invalid topology. Either there is no topology associated with this communicator, or it is not the correct type (e.g., **MPI_CART** when expecting **MPI_GRAPH**).

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

`./src/topol/graph_get.c`

MPI_Graph_map

MPI_Graph_map

MPI_Graph_map — Maps process to graph topology information

Synopsis

```
int MPI_Graph_map ( MPI_Comm comm_old, int nnodes, int *index, int *edges,
                    int *newrank )
```

Input Parameters

comm	input communicator (handle)
nnodes	number of graph nodes (integer)
index	integer array specifying the graph structure, see MPI_GRAPH_CREATE
edges	integer array specifying the graph structure

Output Parameter

newrank	reordered rank of the calling process; MPI_UNDEFINED if the calling process does not belong to graph (integer)
----------------	---

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_TOPOLOGY

Invalid topology. Either there is no topology associated with this communicator, or it is not the correct type (e.g., **MPI_CART** when expecting **MPI_GRAPH**).

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

`./src/topol/graph_map.c`

Synopsis

```
int MPI_Graph_neighbors ( MPI_Comm comm, int rank, int maxneighbors,
                         int *neighbors )
```

Input Parameters

comm communicator with graph topology (handle)
rank rank of process in group of comm (integer)
maxneighbors size of array neighbors (integer)

Output Parameters

neighbors ranks of processes that are neighbors to specified process (array of integer)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_TOPOLOGY

Invalid topology. Either there is no topology associated with this communicator, or it is not the correct type (e.g., **MPI_CART** when expecting **MPI_GRAPH**).

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_SOURCE**.

Location

`./src/topol/graph_nbr.c`

MPI_Graph_neighbors_count	MPI_Graph_neighbors_count
----------------------------------	----------------------------------

MPI_Graph_neighbors_count — Returns the number of neighbors of a node associated with a graph topology

Synopsis

```
int MPI_Graph_neighbors_count ( MPI_Comm comm, int rank, int *nneighbors )
```

Input Parameters

comm	communicator with graph topology (handle)
rank	rank of process in group of comm (integer)

Output Parameter

nneighbors	number of neighbors of specified process (integer)
-------------------	--

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_TOPOLOGY

Invalid topology. Either there is no topology associated with this communicator, or it is not the correct type (e.g., **MPI_CART** when expecting **MPI_GRAPH**).

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_SOURCE**.

Location

`./src/topol/graphnbrcnt.c`

MPI_Graphdims_get	MPI_Graphdims_get
--------------------------	--------------------------

MPI_Graphdims_get — Retrieves graph topology information associated with a communicator

Synopsis

```
int MPI_Graphdims_get ( MPI_Comm comm, int *nnodes, int *nedges )
```

Input Parameters

comm communicator for group with graph structure (handle)

Output Parameter

nnodes	number of nodes in graph (integer)
nedges	number of edges in graph (integer)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_TOPOLOGY

Invalid topology. Either there is no topology associated with this communicator, or it is not the correct type (e.g., **MPI_CART** when expecting **MPI_GRAPH**).

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

`./src/topol/graphdimsget.c`

MPI_Group_compare	MPI_Group_compare
MPI_Group_compare — Compares two groups	

Synopsis

```
int MPI_Group_compare ( MPI_Group group1, MPI_Group group2, int *result )
```

Input Parameters

group1	group1 (handle)
group2	group2 (handle)

Output Parameter

result	integer which is MPI_IDENT if the order and members of the two groups are the same, MPI_SIMILAR if only the members are the same, and MPI_UNEQUAL otherwise
---------------	--

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_GROUP

Null group passed to function.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

`./src/context/groupcompare.c`

MPI_Group_difference	MPI_Group_difference
-----------------------------	-----------------------------

MPI_Group_difference — Makes a group from the difference of two groups

Synopsis

```
int MPI_Group_difference ( MPI_Group group1, MPI_Group group2,
                           MPI_Group *group_out )
```

Input Parameters

group1	first group (handle)
group2	second group (handle)

Output Parameter

newgroup	difference group (handle)
-----------------	---------------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_GROUP

Null group passed to function.

MPI_ERR_INTERN

This error is returned when some part of the MPICH implementation is unable to acquire memory.

See Also

MPI_Group_free

Location

```
./src/context/group_diff.c
```

MPI_Group_excl

MPI_Group_excl

MPI_Group_excl — Produces a group by reordering an existing group and taking only unlisted members

Synopsis

```
int MPI_Group_excl ( MPI_Group group, int n, int *ranks, MPI_Group *newgroup )
```

Input Parameters

group	group (handle)
n	number of elements in array ranks (integer)
ranks	array of integer ranks in group not to appear in newgroup

Output Parameter

newgroup	new group derived from above, preserving the order defined by group (handle)
-----------------	---

Note

Currently, each of the ranks to exclude must be a valid rank in the group and all elements must be distinct or the function is erroneous. This restriction is per the draft.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_GROUP

Null group passed to function.

MPI_ERR_INTERN

This error is returned when some part of the MPICH implementation is unable to acquire memory.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_SOURCE**.

See Also

MPI_Group_free

Location

`./src/context/group_excl.c`

MPI_Group_free

MPI_Group_free

MPI_Group_free — Frees a group

Synopsis

```
int MPI_Group_free ( MPI_Group *group )
```

Input Parameter

group group (handle)

Notes

On output, group is set to **MPI_GROUP_NULL**.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

MPI_ERR_ARG

This error class is associated with an error code that indicates that an attempt was made to free one of the permanent groups.

Location

```
./src/context/group_free.c
```

MPI_Group_incl

MPI_Group_incl

MPI_Group_incl— Produces a group by reordering an existing group and taking only listed members

Synopsis

```
int MPI_Group_incl ( MPI_Group group, int n, int *ranks, MPI_Group *group_out )
```

Input Parameters

group	group (handle)
n	number of elements in array ranks (and size of newgroup) (integer)
ranks	ranks of processes in group to appear in newgroup (array of integers)

Output Parameter

newgroup	new group derived from above, in the order defined by ranks (handle)
-----------------	---

Note

This implementation does not currently check to see that the list of ranks to ensure that there are no duplicates.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may

be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_GROUP

Null group passed to function.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

MPI_ERR_INTERN

This error is returned when some part of the MPICH implementation is unable to acquire memory.

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_SOURCE**.

See Also

MPI_Group_free

Location

`./src/context/group_incl.c`

MPI_Group_intersection**MPI_Group_intersection**

MPI_Group_intersection — Produces a group as the intersection of two existing groups

Synopsis

```
int MPI_Group_intersection ( MPI_Group group1, MPI_Group group2,
                           MPI_Group *group_out )
```

Input Parameters

group1	first group (handle)
group2	second group (handle)

Output Parameter

newgroup	intersection group (handle)
-----------------	-----------------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_GROUP`

Null group passed to function.

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

See Also

`MPI_Group_free`

Location

`./src/context/group_inter.c`

`MPI_Group_range_excl`

`MPI_Group_range_excl`

`MPI_Group_range_excl`— Produces a group by excluding ranges of processes from an existing group

Synopsis

```
int MPI_Group_range_excl ( MPI_Group group, int n, int ranges[][3],
                           MPI_Group *newgroup )
```

Input Parameters

<code>group</code>	group (handle)
<code>n</code>	number of elements in array <code>ranks</code> (integer)
<code>ranges</code>	a one-dimensional array of integer triplets of the form (first rank, last rank, stride), indicating the ranks in <code>group</code> of processes to be excluded from the output group <code>newgroup</code> .

Output Parameter

<code>newgroup</code>	new group derived from above, preserving the order in <code>group</code> (handle)
-----------------------	---

Note

Currently, each of the ranks to exclude must be a valid rank in the group and all elements must be distinct or the function is erroneous. This restriction is per the draft.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_GROUP`

Null group passed to function.

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

`MPI_ERR_RANK`

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_SOURCE`.

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

See Also

`MPI_Group_free`

Location

`./src/context/group_recl.c`

`MPI_Group_range_incl`

`MPI_Group_range_incl`

`MPI_Group_range_incl` — Creates a new group from ranges of ranks in an existing group

Synopsis

```
int MPI_Group_range_incl ( MPI_Group group, int n, int ranges[][3],
                           MPI_Group *newgroup )
```

Input Parameters

group group (handle)
n number of triplets in array **ranges** (integer)
ranges a one-dimensional array of integer triplets, of the form (first rank, last rank, stride) indicating ranks in **group** or processes to be included in **newgroup**

Output Parameter

newgroup new group derived from above, in the order defined by **ranges** (handle)

Note

This implementation does not currently check to see that the list of ranges to include are valid ranks in the group.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_GROUP

Null group passed to function.

MPI_ERR_INTERN

This error is returned when some part of the MPICH implementation is unable to acquire memory.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_SOURCE**.

See Also

MPI_Group_free

Location

```
./src/context/group_rincl.c
```

MPI_Group_rank	MPI_Group_rank
MPI_Group_rank — Returns the rank of this process in the given group	

Synopsis

```
int MPI_Group_rank ( MPI_Group group, int *rank )
```

Input Parameters

group group (handle)

Output Parameter

rank rank of the calling process in group, or **MPI_UNDEFINED** if the process is not a member (integer)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_GROUP

Null group passed to function.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

```
./src/context/group_rank.c
```

MPI_Group_size	MPI_Group_size
-----------------------	-----------------------

MPI_Group_size — Returns the size of a group

Synopsis

```
int MPI_Group_size ( MPI_Group group, int *size )
```

Input Parameters

group	group (handle) Output Parameter:
size	number of processes in the group (integer)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_GROUP

Null group passed to function.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

`./src/context/group_size.c`

MPI_Group_translate_ranks	MPI_Group_translate_ranks
----------------------------------	----------------------------------

MPI_Group_translate_ranks — Translates the ranks of processes in one group to those in another group

Synopsis

```
int MPI_Group_translate_ranks ( MPI_Group group_a, int n, int *ranks_a,
                               MPI_Group group_b, int *ranks_b )
```

Input Parameters

group1	group1 (handle)
n	number of ranks in ranks1 and ranks2 arrays (integer)
ranks1	array of zero or more valid ranks in group1
group2	group2 (handle)

Output Parameter

ranks2	array of corresponding ranks in group2, MPI_UNDEFINED when no correspondence exists.
---------------	---

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_GROUP

Null group passed to function.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_SOURCE**.

Location

`./src/context/group_tranks.c`

MPI_Group_union

MPI_Group_union

MPI_Group_union — Produces a group by combining two groups

Synopsis

```
int MPI_Group_union ( MPI_Group group1, MPI_Group group2,
                      MPI_Group *group_out )
```

Input Parameters

group1	first group (handle)
group2	second group (handle)

Output Parameter

newgroup	union group (handle)
-----------------	----------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_GROUP

Null group passed to function.

MPI_ERR_INTERN

This error is returned when some part of the MPICH implementation is unable to acquire memory.

See Also

MPI_Group_free

Location

`./src/context/group_union.c`

MPI_Ibsend

MPI_Ibsend

MPI_Ibsend — Starts a nonblocking buffered send

Synopsis

```
int MPI_Ibsend( void *buf, int count, MPI_Datatype datatype, int dest, int tag,
                 MPI_Comm comm, MPI_Request *request )
```

Input Parameters

buf	initial address of send buffer (choice)
count	number of elements in send buffer (integer)
datatype	datatype of each send buffer element (handle)
dest	rank of destination (integer)
tag	message tag (integer)
comm	communicator (handle)

Output Parameter

request	communication request (handle)
----------------	--------------------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted **MPI_Datatype** (see **MPI_Type_commit**).

MPI_ERR_TAG

Invalid tag argument. Tags must be non-negative; tags in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_TAG**. The largest tag value is available through the attribute **MPI_TAG_UB**.

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_SOURCE**.

MPI_ERR_BUFFER

Invalid buffer pointer. Usually a null buffer where one is not valid.

Location

`./src/pt2pt/ibsend.c`

MPI_Info_c2f**MPI_Info_c2f**

MPI_Info_c2f — Translates a C info handle to a Fortran info handle

Synopsis

```
MPI_Fint MPI_Info_c2f(MPI_Info info)
```

Input Parameters

info C info handle (integer)

Return Value

Fortran info handle (handle)

Location

`./src/misc2/info_c2f.c`

MPI_Info_create**MPI_Info_create**

MPI_Info_create — Creates a new info object

Synopsis

```
int MPI_Info_create(MPI_Info *info)
```

Output Parameters

info info object (handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./src/misc2/info_create.c
```

MPI_Info_delete

MPI_Info_delete

MPI_Info_delete — Deletes a (key,value) pair from info

Synopsis

```
int MPI_Info_delete(MPI_Info info, char *key)
```

Input Parameters

info	info object (handle)
key	key (string)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./src/misc2/info_delete.c
```

MPI_Info_dup

MPI_Info_dup

MPI_Info_dup — Returns a duplicate of the info object

Synopsis

```
int MPI_Info_dup(MPI_Info info, MPI_Info *newinfo)
```

Input Parameters

info	info object (handle)
-------------	----------------------

Output Parameters

newinfo	duplicate of info object (handle)
----------------	-----------------------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./src/misc2/info_dup.c
```

MPI_Info_f2c

MPI_Info_f2c

MPI_Info_f2c — Translates a Fortran info handle to a C info handle

Synopsis

```
MPI_Info MPI_Info_f2c(MPI_Fint info)
```

Input Parameters

info Fortran info handle (integer)

Return Value

C info handle (handle)

Location

```
./src/misc2/info_f2c.c
```

MPI_Info_free

MPI_Info_free

MPI_Info_free — Frees an info object

Synopsis

```
int MPI_Info_free(MPI_Info *info)
```

Input Parameters

info info object (handle)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./src/misc2/info_free.c
```

MPI_Info_get

MPI_Info_get

MPI_Info_get — Retrieves the value associated with a key

Synopsis

```
int MPI_Info_get(MPI_Info info, char *key, int valuelen, char *value, int *flag)
```

Input Parameters

info	info object (handle)
key	key (string)
valuelen	length of value argument (integer)

Output Parameters

value	value (string)
flag	true if key defined, false if not (boolean)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./src/misc2/info_get.c
```

MPI_Info_get_nkeys

MPI_Info_get_nkeys

MPI_Info_get_nkeys — Returns the number of currently defined keys in info

Synopsis

```
int MPI_Info_get_nkeys(MPI_Info info, int *nkeys)
```

Input Parameters

info info object (handle)

Output Parameters

nkeys number of defined keys (integer)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./src/misc2/info_getnks.c`

MPI_Info_get_nthkey

MPI_Info_get_nthkey

MPI_Info_get_nthkey — Returns the nth defined key in info

Synopsis

```
int MPI_Info_get_nthkey(MPI_Info info, int n, char *key)
```

Input Parameters

info info object (handle)
n key number (integer)

Output Parameters

key key (string)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./src/misc2/info_getnths.c
```

MPI_Info_get_valuelen	MPI_Info_get_valuelen
------------------------------	------------------------------

MPI_Info_get_valuelen — Retrieves the length of the value associated with a key

Synopsis

```
int MPI_Info_get_valuelen(MPI_Info info, char *key, int *valuelen, int *flag)
```

Input Parameters

info	info object (handle)
key	key (string)

Output Parameters

valuelen	length of value argument (integer)
flag	true if key defined, false if not (boolean)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./src/misc2/info_getvln.c
```

MPI_Info_set	MPI_Info_set
---------------------	---------------------

MPI_Info_set — Adds a (key,value) pair to info

Synopsis

```
int MPI_Info_set(MPI_Info info, char *key, char *value)
```

Input Parameters

info	info object (handle)
key	key (string)
value	value (string)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./src/misc2/info_set.c
```

`MPI_Init`

`MPI_Init`

`MPI_Init` — Initialize the MPI execution environment

Synopsis

```
int MPI_Init(int *argc, char ***argv)
```

Input Parameters

<code>argc</code>	Pointer to the number of arguments
<code>argv</code>	Pointer to the argument vector

Command line arguments

MPI specifies no command-line arguments but does allow an MPI implementation to make use of them.

<code>-mpiqueue</code>	print out the state of the message queues when <code>MPI_FINALIZE</code> is called. All processors print; the output may be hard to decipher. This is intended as a debugging aid.
<code>-mpiversion</code>	print out the version of the implementation (<i>not</i> of MPI), including the arguments that were used with configure.
<code>-mpinice nn</code>	Increments the nice value by <code>nn</code> (lowering the priority of the program by <code>nn</code>). <code>nn</code> must be positive (except for root). Not all systems support this argument; those that do not will ignore it.
<code>-mpedbg</code>	Start a debugger in an xterm window if there is an error (either detected by MPI or a normally fatal signal). This works only if MPICH was configured with <code>-mpedbg</code> . CURRENTLY DISABLED. If you have TotalView, -mpichtv or mpirun -tv will give you a better environment anyway.
<code>-mpimem</code>	If MPICH was built with <code>-DMPIR_DEBUG_MEM</code> , this checks all malloc and free operations (internal to MPICH) for signs of injury to the memory allocation areas.
<code>-mpidb options</code>	Activate various debugging options. Some require that MPICH have been built with special options. These are intended for debugging MPICH, not for debugging user programs. The available options include:
<code>mem</code>	- Enable dynamic memory tracing of internal MPI objects
<code>memall</code>	- Generate output of all memory allocation/deallocation
<code>ptr</code>	- Enable tracing of internal MPI pointer conversions
<code>rank n</code>	- Limit subsequent <code>-mpidb</code> options to on the process with rank <code>n</code>

```

the specified rank in MPI_COMM_WORLD. A rank of -1
selects all of MPI_COMM_WORLD.
ref      - Trace use of internal MPI objects
reffile filename - Trace use of internal MPI objects with output
                  to the indicated file
trace    - Trace routine calls

```

Notes

Note that the Fortran binding for this routine has only the error return argument (`MPI_INIT(ierr)`)

Because the Fortran and C versions of `MPI_Init` are different, there is a restriction on who can call `MPI_Init`. The version (Fortran or C) must match the main program. That is, if the main program is in C, then the C version of `MPI_Init` must be called. If the main program is in Fortran, the Fortran version must be called.

On exit from this routine, all processes will have a copy of the argument list. This is *not required* by the MPI standard, and truly portable codes should not rely on it. This is provided as a service by this implementation (an MPI implementation is allowed to distribute the command line arguments but is not required to).

Command line arguments are not provided to Fortran programs. More precisely, non-standard Fortran routines such as `getarg` and `iargc` have undefined behavior in MPI and in this implementation.

The MPI standard does not say what a program can do before an `MPI_INIT` or after an `MPI_FINALIZE`. In the MPICH implementation, you should do as little as possible. In particular, avoid anything that changes the external state of the program, such as opening files, reading standard input or writing to standard output.

Signals used

The MPI standard requires that all signals used be documented. The MPICH implementation itself uses no signals, but some of the software that MPICH relies on may use some signals. The list below is partial and should be independently checked if you (and any package that you use) depend on particular signals.

IBM POE/MPL for SP2

SIGHUP, SIGINT, SIGQUIT, SIGFPE, SIGSEGV, SIGPIPE, SIGALRM, SIGTERM, SIGIO

-mpedbg switch

SIGQUIT, SIGILL, SIGFPE, SIGBUS, SIGSEGV, SIGSYS

Meiko CS2

SIGUSR2

ch_p4 device

SIGUSR1

The ch_p4 device also catches SIGINT, SIGFPE, SIGBUS, and SIGSEGV; this helps the p4 device (and MPICH) more gracefully abort a failed program.

Intel Paragon (ch_nx and nx device)

SIGUSR2

Shared Memory (ch_shmem device)

SIGCHLD

Note that if you are using software that needs the same signals, you may find that there is no way to use that software with the MPI implementation. The signals that cause the most trouble for applications include **SIGIO**, **SIGALRM**, and **SIGPIPE**. For example, using **SIGIO** and **SIGPIPE** may prevent X11 routines from working.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_OTHER

This error class is associated with an error code that indicates that an attempt was made to call **MPI_Init** a second time. **MPI_Init** may only be called once in a program.

Location

```
./src/env/init.c
```

MPI_Init_thread**MPI_Init_thread**

MPI_Init_thread — Initialize the MPI execution environment

Synopsis

```
int MPI_Init_thread(int *argc, char ***argv, int required, int *provided )
```

Input Parameters

argc	Pointer to the number of arguments
argv	Pointer to the argument vector
required	Level of desired thread support

Output Parameter

provided	Level of provided thread support
-----------------	----------------------------------

Command line arguments

MPI specifies no command-line arguments but does allow an MPI implementation to make use of them. See `MPI_INIT` for a description of the command line arguments supported by `MPI_INIT` and `MPI_INIT_THREAD`.

Notes

Note that the Fortran binding for this routine does not have the `argc` and `argv` arguments.

`(MPI_INIT_THREAD(required, provided, ierror))`

Currently, MPICH places the same restrictions on `MPI_INIT_THREAD` as on `MPI_INIT` (see the `MPI_INIT` man page). When MPICH fully supports MPI-2, this restriction will be removed (as required by the MPI-2 standard).

Signals used

The MPI standard requires that all signals used be documented. The MPICH implementation itself uses no signals, but some of the software that MPICH relies on may use some signals. The list below is partial and should be independently checked if you (and any package that you use) depend on particular signals.

IBM POE/MPL for SP2

SIGHUP, SIGINT, SIGQUIT, SIGFPE, SIGSEGV, SIGPIPE, SIGALRM, SIGTERM, SIGIO

-mpedbg switch

SIGQUIT, SIGILL, SIGFPE, SIGBUS, SIGSEGV, SIGSYS

Meiko CS2

SIGUSR2

ch_p4 device

SIGUSR1

The ch_p4 device also catches SIGINT, SIGFPE, SIGBUS, and SIGSEGV; this helps the p4 device (and MPICH) more gracefully abort a failed program.

Intel Paragon (ch_nx and nx device)

SIGUSR2

Shared Memory (ch_shmem device)

SIGCHLD

Note that if you are using software that needs the same signals, you may find that there is no way to use that software with the MPI implementation. The signals that cause the most trouble for applications include `SIGIO`, `SIGALRM`, and `SIGPIPE`. For example, using `SIGIO` and `SIGPIPE` may prevent X11 routines from working.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_OTHER

This error class is associated with an error code that indicates that an attempt was made to call **MPI_Init** a second time. **MPI_Init** may only be called once in a program.

Location

```
./src/env/initthread.c
```

MPI_Initialized

MPI_Initialized

MPI_Initialized — Indicates whether **MPI_Init** has been called.

Synopsis

```
int MPI_Initialized( int *flag )
```

Output Parameter

flag Flag is true if **MPI_Init** has been called and false otherwise.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./src/env/initialize.c
```

MPI_Intercomm_create

MPI_Intercomm_create

MPI_Intercomm_create — Creates an intercommunicator from two intracomunicators

Synopsis

```
int MPI_Intercomm_create ( MPI_Comm local_comm, int local_leader,
                           MPI_Comm peer_comm, int remote_leader, int tag,
                           MPI_Comm *comm_out )
```

Input Parameters

local_comm	Local (intra)communicator
local_leader	Rank in local_comm of leader (often 0)
peer_comm	Remote communicator
remote_leader	Rank in peer_comm of remote leader (often 0)
tag	Message tag to use in constructing intercommunicator; if multiple MPI_Intercomm_create s are being made, they should use different tags (more precisely, ensure that the local and remote leaders are using different tags for each MPI_intercomm_create).

Output Parameter

comm_out	Created intercommunicator
-----------------	---------------------------

Notes

The MPI 1.1 Standard contains two mutually exclusive comments on the input intracomunicators. One says that their respective groups must be disjoint; the other that the leaders can be the same process. After some discussion by the MPI Forum, it has been decided that the groups must be disjoint. Note that the *reason* given for this in the standard is *not* the reason for this choice; rather, the *other* operations on intercommunicators (like **MPI_Intercomm_merge**) do not make sense if the groups are not disjoint.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Algorithm

- 1) Allocate a send context, an inter
coll context, and an intra-coll context
- 2) Send "send_context" and lrank_to_grank list from local comm group
if I'm the local_leader.
- 3) If I'm the local leader, then wait on the posted sends and receives
to complete. Post the receive for the remote group information and wait for it to
complete.
- 4) Broadcast information received from the remote leader.
. 5) Create the inter_communicator from the information we now have.

An inter communicator ends up with three levels of communicators. The inter-communicator returned to the user, a "collective" inter-communicator that can be used for safe communications between local & remote groups, and a collective intra-communicator that can be used to allocate new contexts during the merge and dup operations.

For the resulting inter-communicator, `comm_out`

```
comm_out           = inter-communicator
comm_out->comm_coll = "collective" inter-communicator
comm_out->comm_coll->comm_coll = safe collective intra-communicator
```

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_TAG`

Invalid tag argument. Tags must be non-negative; tags in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_TAG`. The largest tag value is available through the attribute `MPI_TAG_UB`.

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

`MPI_ERR_RANK`

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_SOURCE`.

See Also

`MPI_Intercomm_merge`, `MPI_Comm_free`, `MPI_Comm_remote_group`,
`MPI_Comm_remote_size`

Location

`./src/context/ic_create.c`

MPI_Intercomm_merge

MPI_Intercomm_merge

MPI_Intercomm_merge — Creates an intracommunicator from an intercommunicator

Synopsis

```
int MPI_Intercomm_merge ( MPI_Comm comm, int high, MPI_Comm *comm_out )
```

Input Parameters

comm Intercommunicator
high Used to order the groups of the two intracomunicators within comm when creating the new communicator.

Output Parameter

comm_out Created intracommunicator

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Algorithm

- 1) Allocate two contexts
- 2) Local and remote group leaders swap high values
- 3) Determine the high value.
- 4) Merge the two groups and make the intra-communicator

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

See Also

`MPI_Intercomm_create`, `MPI_Comm_free`

Location

`./src/context/ic_merge.c`

MPI_Iprobe	MPI_Iprobe
-------------------	-------------------

MPI_Iprobe — Nonblocking test for a message

Synopsis

```
int MPI_Iprobe( int source, int tag, MPI_Comm comm, int *flag,
                 MPI_Status *status )
```

Input Parameters

source	source rank, or MPI_ANY_SOURCE (integer)
tag	tag value or MPI_ANY_TAG (integer)
comm	communicator (handle)

Output Parameter

flag	(logical)
status	status object (Status)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_TAG

Invalid tag argument. Tags must be non-negative; tags in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_TAG**. The largest tag value is available through the attribute **MPI_TAG_UB**.

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_SOURCE**.

Location

`./src/pt2pt/iprobe.c`

MPI_Irecv

MPI_Irecv

MPI_Irecv — Begins a nonblocking receive

Synopsis

```
int MPI_Irecv( void *buf, int count, MPI_Datatype datatype, int source,
               int tag, MPI_Comm comm, MPI_Request *request )
```

Input Parameters

buf	initial address of receive buffer (choice)
count	number of elements in receive buffer (integer)
datatype	datatype of each receive buffer element (handle)
source	rank of source (integer)
tag	message tag (integer)
comm	communicator (handle)

Output Parameter

request	communication request (handle)
----------------	--------------------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./src/pt2pt/irecv.c`

MPI_Irsend

MPI_Irsend

MPI_Irsend — Starts a nonblocking ready send

Synopsis

```
int MPI_Irsend( void *buf, int count, MPI_Datatype datatype, int dest,
                int tag, MPI_Comm comm, MPI_Request *request )
```

Input Parameters

buf	initial address of send buffer (choice)
count	number of elements in send buffer (integer)
datatype	datatype of each send buffer element (handle)
dest	rank of destination (integer)
tag	message tag (integer)
comm	communicator (handle) Output Parameter:
request	communication request (handle)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted `MPI_Datatype` (see `MPI_Type_commit`).

`MPI_ERR_TAG`

Invalid tag argument. Tags must be non-negative; tags in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_TAG`. The largest tag value is available through the attribute `MPI_TAG_UB`.

`MPI_ERR_RANK`

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_SOURCE`.

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

Location

`./src/pt2pt/irsend.c`

MPI_Isend**MPI_Isend**

MPI_Isend — Begins a nonblocking send

Synopsis

```
int MPI_Isend( void *buf, int count, MPI_Datatype datatype, int dest, int tag,
                MPI_Comm comm, MPI_Request *request )
```

Input Parameters

buf	initial address of send buffer (choice)
count	number of elements in send buffer (integer)
datatype	datatype of each send buffer element (handle)
dest	rank of destination (integer)
tag	message tag (integer)
comm	communicator (handle)

Output Parameter

request	communication request (handle)
----------------	--------------------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted **MPI_Datatype** (see **MPI_Type_commit**).

MPI_ERR_TAG

Invalid tag argument. Tags must be non-negative; tags in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_TAG`. The largest tag value is available through the attribute `MPI_TAG_UB`.

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_SOURCE`.

MPI_ERR_INTERN

This error is returned when some part of the MPICH implementation is unable to acquire memory.

Location

```
./src/pt2pt/isend.c
```

MPI_Issend**MPI_Issend**

MPI_Issend — Starts a nonblocking synchronous send

Synopsis

```
int MPI_Issend( void *buf, int count, MPI_Datatype datatype, int dest,
                int tag, MPI_Comm comm, MPI_Request *request )
```

Input Parameters

buf	initial address of send buffer (choice)
count	number of elements in send buffer (integer)
datatype	datatype of each send buffer element (handle)
dest	rank of destination (integer)
tag	message tag (integer)
comm	communicator (handle)

Output Parameter

request	communication request (handle)
----------------	--------------------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler

may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

`MPI_ERR_TAG`

Invalid tag argument. Tags must be non-negative; tags in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_TAG`. The largest tag value is available through the attribute `MPI_TAG_UB`.

`MPI_ERR_RANK`

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_SOURCE`.

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

Location

`./src/pt2pt/issend.c`

`MPI_Keyval_create`

`MPI_Keyval_create`

`MPI_Keyval_create` — Generates a new attribute key

Synopsis

```
int MPI_Keyval_create (
    MPI_Copy_function *copy_fn,
    MPI_Delete_function *delete_fn,
    int *keyval,
    void *extra_state )
```

Input Parameters

<code>copy_fn</code>	Copy callback function for <code>keyval</code>
<code>delete_fn</code>	Delete callback function for <code>keyval</code>
<code>extra_state</code>	Extra state for callback functions

Output Parameter

<code>keyval</code>	key value for future access (integer)
---------------------	---------------------------------------

Notes

Key values are global (available for any and all communicators).

There are subtle differences between C and Fortran that require that the `copy_fn` be written in the same language that `MPI_Keyval_create` is called from. This should not be a problem for most users; only programmers using both Fortran and C in the same program need to be sure that they follow this rule.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

Location

`./src/context/keyvalcreate.c`

`MPI_Keyval_free`

`MPI_Keyval_free`

`MPI_Keyval_free` — Frees attribute key for communicator cache attribute

Synopsis

```
int MPI_Keyval_free ( int *keyval )
```

Input Parameter

<code>keyval</code>	Frees the integer key value (integer)
---------------------	---------------------------------------

Note

Key values are global (they can be used with any and all communicators)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

`MPI_ERR_ARG`

This error class is associated with an error code that indicates that an attempt was made to free one of the permanent keys.

See Also

`MPI_Keyval_create`

Location

`./src/context/keyval_free.c`

`MPI_NULL_COPY_FN`

`MPI_NULL_COPY_FN`

`MPI_NULL_COPY_FN` — A function to not copy attributes

Notes

See discussion of `MPI_Keyval_create` for the use of this function.

Location

`./src/context/null_copyfn.c`

MPI_NULL_DELETE_FN**MPI_NULL_DELETE_FN**

MPI_NULL_DELETE_FN — A function to not delete attributes

Input Parameters

comm	Communicator
keyval	Key value
attr	attribute
extra_state	User-defined state to give user functions

Notes

See discussion of **MPI_Keyval_create** for the use of this function.

Location

`./src/context/null_del_fn.c`

MPI_Op_create**MPI_Op_create**

MPI_Op_create — Creates a user-defined combination function handle

Synopsis

```
int MPI_Op_create(
    MPI_User_function *function,
    int commute,
    MPI_Op *op )
```

Input Parameters

function	user defined function (function)
commute	true if commutative; false otherwise.

Output Parameter

op	operation (handle)
-----------	--------------------

Notes on the user function

The calling list for the user function type is

```
typedef void (MPI_User_function) ( void * a,
                                  void * b, int * len, MPI_Datatype * );
```

where the operation is $b[i] = a[i] \text{ op } b[i]$, for $i=0, \dots, \text{len}-1$. A pointer to the datatype given to the MPI collective computation routine (i.e., **MPI_Reduce**, **MPI_Allreduce**, **MPI_Scan**, or **MPI_Reduce_scatter**) is also passed to the user-specified routine.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Notes on collective operations

The reduction functions (`MPI_Op`) do not return an error value. As a result, if the functions detect an error, all they can do is either call `MPI_Abort` or silently skip the problem. Thus, if you change the error handler from `MPI_ERRORS_ARE_FATAL` to something else, for example, `MPI_ERRORS_RETURN`, then no error may be indicated.

The reason for this is the performance problems in ensuring that all collective routines return the same error value.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

See Also

`MPI_Op_free`

Location

`./src/coll/opcreate.c`

`MPI_Op_free`

`MPI_Op_free`

`MPI_Op_free` — Frees a user-defined combination function handle

Synopsis

```
int MPI_Op_free( MPI_Op *op )
```

Input Parameter

op operation (handle)

Notes

op is set to **MPI_OP_NULL** on exit.

Null Handles

The MPI 1.1 specification, in the section on opaque objects, explicitly

disallows freeing a null communicator. The text from the standard is

A null handle argument is an erroneous IN argument in MPI calls, unless an exception is explicitly stated in the text that defines the function. Such exception is allowed for handles to request objects in Wait and Test calls (sections Communication Completion and Multiple Completions). Otherwise, a null handle can only be passed to a function that allocates a new object and returns a reference to it in the handle.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

MPI_ERR_ARG

Invalid argument; the error code associated with this error indicates an attempt to free an MPI permanent operation (e.g., **MPI_SUM**). *N/ /*N

MPI_ERR_PERM_KEY

Invalid argument; the error code associated with this error indicates an attempt to free or change an MPI permanent keyval (e.g., **MPI_TAG_UB**). *N/ /*N

MPI_ERR_UNKNOWN

Unknown error. You should never see this. If you do, report it to
mpi-bugs@mcs.anl.gov.

See Also**MPI_Op_create****Location**`./src/coll/opfree.c`**MPI_Pack****MPI_Pack****MPI_Pack** — Packs a datatype into contiguous memory**Synopsis**

```
int MPI_Pack ( void *inbuf, int incount, MPI_Datatype datatype,
               void *outbuf, int outcount, int *position, MPI_Comm comm )
```

Input Parameters

inbuf	input buffer start (choice)
incount	number of input data items (integer)
datatype	datatype of each input data item (handle)
outcount	output buffer size, in bytes (integer)
position	current position in buffer, in bytes (integer)
comm	communicator for packed message (handle)

Output Parameter

outbuf	output buffer start (choice)
---------------	------------------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

See Also

`MPI_Unpack`, `MPI_Pack_size`

Location

`./src/pt2pt/pack.c`

<code>MPI_Pack_size</code>	<code>MPI_Pack_size</code>
----------------------------	----------------------------

`MPI_Pack_size` — Returns the upper bound on the amount of space needed to pack a message

Synopsis

```
int MPI_Pack_size ( int incount, MPI_Datatype datatype, MPI_Comm comm,
                    int *size )
```

Input Parameters

<code>incount</code>	count argument to packing call (integer)
<code>datatype</code>	datatype argument to packing call (handle)
<code>comm</code>	communicator argument to packing call (handle)

Output Parameter

<code>size</code>	upper bound on size of packed message, in bytes (integer)
-------------------	---

Notes

The MPI standard document describes this in terms of `MPI_Pack`, but it applies to both `MPI_Pack` and `MPI_Unpack`. That is, the value `size` is the maximum that is needed by either `MPI_Pack` or `MPI_Unpack`.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call
(not even allowed in `MPI_Comm_rank`).

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted `MPI_Datatype` (see
`MPI_Type_commit`).

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific
error class (e.g., `MPI_ERR_RANK`).

Location

`./src/pt2pt/pack_size.c`

`MPI_Pcontrol`

`MPI_Pcontrol`

`MPI_Pcontrol` — Controls profiling

Synopsis

```
int MPI_Pcontrol( int level )
```

Input Parameters

<code>level</code>	Profiling level
--------------------	-----------------

Notes

This routine provides a common interface for profiling control. The interpretation of `level` and any other arguments is left to the profiling library.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

```
./src/profile/pcontrol.c
```

MPI_Probe	MPI_Probe
------------------	------------------

MPI_Probe — Blocking test for a message

Synopsis

```
int MPI_Probe( int source, int tag, MPI_Comm comm, MPI_Status *status )
```

Input Parameters

source	source rank, or <code>MPI_ANY_SOURCE</code> (integer)
tag	tag value or <code>MPI_ANY_TAG</code> (integer)
comm	communicator (handle)

Output Parameter

status	status object (Status)
--------	------------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

MPI_ERR_TAG

Invalid tag argument. Tags must be non-negative; tags in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_TAG`. The largest tag value is available through the attribute `MPI_TAG_UB`.

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_SOURCE`.

Location

```
./src/pt2pt/probe.c
```

MPI_Recv**MPI_Recv**

MPI_Recv — Basic receive

Synopsis

```
int MPI_Recv( void *buf, int count, MPI_Datatype datatype, int source,
              int tag, MPI_Comm comm, MPI_Status *status )
```

Output Parameters

buf	initial address of receive buffer (choice)
status	status object (Status)

Input Parameters

count	maximum number of elements in receive buffer (integer)
datatype	datatype of each receive buffer element (handle)
source	rank of source (integer)
tag	message tag (integer)
comm	communicator (handle)

Notes

The `count` argument indicates the maximum length of a message; the actual number can be determined with `MPI_Get_count`.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_TAG`

Invalid tag argument. Tags must be non-negative; tags in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_TAG`. The largest tag value is available through the attribute `MPI_TAG_UB`.

`MPI_ERR_RANK`

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_SOURCE`.

Location

`./src/pt2pt/recv.c`

`MPI_Recv_init`

`MPI_Recv_init`

`MPI_Recv_init` — Builds a handle for a receive

Synopsis

```
int MPI_Recv_init( void *buf, int count, MPI_Datatype datatype, int source,
                   int tag, MPI_Comm comm, MPI_Request *request )
```

Input Parameters

<code>buf</code>	initial address of receive buffer (choice)
<code>count</code>	number of elements received (integer)
<code>datatype</code>	type of each element (handle)
<code>source</code>	rank of source or <code>MPI_ANY_SOURCE</code> (integer)
<code>tag</code>	message tag or <code>MPI_ANY_TAG</code> (integer)
<code>comm</code>	communicator (handle)

Output Parameter

request communication request (handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted **MPI_Datatype** (see **MPI_Type_commit**).

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_SOURCE**.

MPI_ERR_TAG

Invalid tag argument. Tags must be non-negative; tags in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_TAG**. The largest tag value is available through the attribute **MPI_TAG_UB**.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_INTERN

This error is returned when some part of the MPICH implementation is unable to acquire memory.

See Also

MPI_Start, **MPI_Request_free**

Location

`./src/pt2pt/create_recv.c`

MPI_Reduce **MPI_Reduce**

MPI_Reduce — Reduces values on all processes to a single value

Synopsis

```
int MPI_Reduce ( void *sendbuf, void *recvbuf, int count,
                  MPI_Datatype datatype, MPI_Op op, int root, MPI_Comm comm )
```

Input Parameters

sendbuf	address of send buffer (choice)
count	number of elements in send buffer (integer)
datatype	data type of elements of send buffer (handle)
op	reduce operation (handle)
root	rank of root process (integer)
comm	communicator (handle)

Output Parameter

recvbuf	address of receive buffer (choice, significant only at root)
----------------	--

Algorithm

This implementation currently uses a simple tree algorithm.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Notes on collective operations

The reduction functions (**MPI_Op**) do not return an error value. As a result, if the functions detect an error, all they can do is either call **MPI_Abort** or silently skip the problem. Thus, if you change the error handler from **MPI_ERRORS_ARE_FATAL** to something else, for example, **MPI_ERRORS_RETURN**, then no error may be indicated.

The reason for this is the performance problems in ensuring that all collective routines return the same error value.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may

be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

MPI_ERR_BUFFER

Invalid buffer pointer. Usually a null buffer where one is not valid.

MPI_ERR_BUFFER

This error class is associated with an error code that indicates that two buffer arguments are *aliased*; that is, they describe overlapping storage (often the exact same storage). This is prohibited in MPI (because it is prohibited by the Fortran standard, and rather than have a separate case for C and Fortran, the MPI Forum adopted the more restrictive requirements of Fortran).

Location

`./src/coll/reduce.c`

MPI_Reduce_scatter

MPI_Reduce_scatter

MPI_Reduce_scatter — Combines values and scatters the results

Synopsis

```
int MPI_Reduce_scatter ( void *sendbuf, void *recvbuf, int *recvcounts,
                         MPI_Datatype datatype, MPI_Op op, MPI_Comm comm )
```

Input Parameters

sendbuf	starting address of send buffer (choice)
recvcounts	integer array specifying the number of elements in result distributed to each process. Array must be identical on all calling processes.
datatype	data type of elements of input buffer (handle)
op	operation (handle)
comm	communicator (handle)

Output Parameter

recvbuf	starting address of receive buffer (choice)
----------------	---

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Notes on collective operations

The reduction functions (`MPI_Op`) do not return an error value. As a result, if the functions detect an error, all they can do is either call `MPI_Abort` or silently skip the problem. Thus, if you change the error handler from `MPI_ERRORS_ARE_FATAL` to something else, for example, `MPI_ERRORS_RETURN`, then no error may be indicated.

The reason for this is the performance problems in ensuring that all collective routines return the same error value.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted `MPI_Datatype` (see `MPI_Type_commit`).

`MPI_ERR_BUFFER`

Invalid buffer pointer. Usually a null buffer where one is not valid.

`MPI_ERR_OP`

Invalid operation. MPI operations (objects of type `MPI_Op`) must either be one of the predefined operations (e.g., `MPI_SUM`) or created with `MPI_Op_create`.

`MPI_ERR_BUFFER`

This error class is associated with an error code that indicates that two buffer arguments are *aliased*; that is, they describe overlapping storage (often the exact same storage). This is prohibited in MPI (because it is prohibited by the Fortran standard, and rather than have a separate case for C and Fortran, the MPI Forum adopted the more restrictive requirements of Fortran).

Location

`./src/coll/red_scat.c`

MPI_Request_c2f**MPI_Request_c2f**

MPI_Request_c2f — Convert a C request to a Fortran request

Synopsis

```
MPI_Fint MPI_Request_c2f( c_request )
MPI_Request  c_request;
```

Input Parameters

c_request Request value in C (handle)

Output Value

f_request Status value in Fortran (Integer)

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

`./src/misc2/requestc2f.c`

MPI_Request_free**MPI_Request_free**

MPI_Request_free — Frees a communication request object

Synopsis

```
int MPI_Request_free( MPI_Request *request )
```

Input Parameter

request communication request (handle)

Notes

This routine is normally used to free persistent requests created with either `MPI_Recv_init` or `MPI_Send_init` and friends. However, it can be used to free a request created with `MPI_Irecv` or `MPI_Isend` and friends; in that case the user can not use the test/wait routines on the request. It is permitted to free an active request. However, once freed, you can not use the request in a wait or test routine (e.g., `MPI_Wait`).

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_REQUEST`

Invalid `MPI_Request`. Either null or, in the case of a `MPI_Start` or `MPI_Startall`, not a persistent request.

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

See Also

also: `MPI_Isend`, `MPI_Irecv`, `MPI_Issend`, `MPI_Ibsend`, `MPI_Irsend`,
`MPI_Recv_init`, `MPI_Send_init`, `MPI_Ssend_init`, `MPI_Rsend_init`, `MPI_Wait`, `MPI_Test`,
`MPI_Waitall`, `MPI_Waitany`, `MPI_Waitsome`, `MPI_Testall`, `MPI_Testany`, `MPI_Testsome`

Location

`./src/pt2pt/commreq_free.c`

`MPI_Rsend`

`MPI_Rsend`

`MPI_Rsend` — Basic ready send

Synopsis

```
int MPI_Rsend( void *buf, int count, MPI_Datatype datatype, int dest,
               int tag, MPI_Comm comm )
```

Input Parameters

buf	initial address of send buffer (choice)
count	number of elements in send buffer (nonnegative integer)
datatype	datatype of each send buffer element (handle)
dest	rank of destination (integer)
tag	message tag (integer)
comm	communicator (handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted **MPI_Datatype** (see **MPI_Type_commit**).

MPI_ERR_TAG

Invalid tag argument. Tags must be non-negative; tags in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_TAG**. The largest tag value is available through the attribute **MPI_TAG_UB**.

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_SOURCE**.

Location

`./src/pt2pt/rsend.c`

MPI_Rsend_init

MPI_Rsend_init

MPI_Rsend_init — Builds a handle for a ready send

Synopsis

```
int MPI_Rsend_init( void *buf, int count, MPI_Datatype datatype, int dest,
                    int tag, MPI_Comm comm, MPI_Request *request )
```

Input Parameters

buf	initial address of send buffer (choice)
count	number of elements sent (integer)
datatype	type of each element (handle)
dest	rank of destination (integer)
tag	message tag (integer)
comm	communicator (handle)

Output Parameter

request	communication request (handle)
----------------	--------------------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted **MPI_Datatype** (see **MPI_Type_commit**).

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_SOURCE**.

MPI_ERR_TAG

Invalid tag argument. Tags must be non-negative; tags in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_TAG**. The largest tag value is available through the attribute **MPI_TAG_UB**.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_INTERN

This error is returned when some part of the MPICH implementation is unable to acquire memory.

See Also

`MPI_Start`, `MPI_Request_free`, `MPI_Send_init`

Location

`./src/pt2pt/rsend_init.c`

MPI_Scan**MPI_Scan**

MPI_Scan — Computes the scan (partial reductions) of data on a collection of processes

Synopsis

```
int MPI_Scan ( void *sendbuf, void *recvbuf, int count, MPI_Datatype datatype,
               MPI_Op op, MPI_Comm comm )
```

Input Parameters

sendbuf	starting address of send buffer (choice)
count	number of elements in input buffer (integer)
datatype	data type of elements of input buffer (handle)
op	operation (handle)
comm	communicator (handle)

Output Parameter

recvbuf	starting address of receive buffer (choice)
----------------	---

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Notes on collective operations

The reduction functions (`MPI_Op`) do not return an error value. As a result, if the functions detect an error, all they can do is either call `MPI_Abort` or silently skip the problem. Thus, if you change the error handler from `MPI_ERRORS_ARE_FATAL` to something else, for example, `MPI_ERRORS_RETURN`, then no error may be indicated.

The reason for this is the performance problems in ensuring that all collective routines return the same error value.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

`MPI_ERR_BUFFER`

Invalid buffer pointer. Usually a null buffer where one is not valid.

`MPI_ERR_BUFSIZE`

This error class is associated with an error code that indicates that two buffer arguments are *aliased*; that is, they describe overlapping storage (often the exact same storage). This is prohibited in MPI (because it is prohibited by the Fortran standard, and rather than have a separate case for C and Fortran, the MPI Forum adopted the more restrictive requirements of Fortran).

Location

`./src/coll/scan.c`

`MPI_Scatter`

`MPI_Scatter`

`MPI_Scatter` — Sends data from one task to all other tasks in a group

Synopsis

```
int MPI_Scatter (
    void *sendbuf,
    int sendcnt,
    MPI_Datatype sendtype,
    void *recvbuf,
    int recvcnt,
    MPI_Datatype recvtype,
    int root,
    MPI_Comm comm )
```

Input Parameters

<code>sendbuf</code>	address of send buffer (choice, significant only at <code>root</code>)
<code>sendcount</code>	number of elements sent to each process (integer, significant only at <code>root</code>)

sendtype	data type of send buffer elements (significant only at root) (handle)
recvcount	number of elements in receive buffer (integer)
recvtype	data type of receive buffer elements (handle)
root	rank of sending process (integer)
comm	communicator (handle)

Output Parameter

recvbuf	address of receive buffer (choice)
----------------	------------------------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted **MPI_Datatype** (see **MPI_Type_commit**).

MPI_ERR_BUFFER

Invalid buffer pointer. Usually a null buffer where one is not valid.

Location

`./src/coll/scatter.c`

MPI_Scatterv

MPI_Scatterv

MPI_Scatterv — Scatters a buffer in parts to all tasks in a group

Synopsis

```
int MPI_Scatterv (
    void *sendbuf,
```

```

int *sendcnts,
int *displs,
MPI_Datatype sendtype,
void *recvbuf,
int recvnt,
MPI_Datatype recvtype,
int root,
MPI_Comm comm )

```

Input Parameters

sendbuf	address of send buffer (choice, significant only at root)
sendcounts	integer array (of length group size) specifying the number of elements to send to each processor
displs	integer array (of length group size). Entry i specifies the displacement (relative to sendbuf from which to take the outgoing data to process i)
sendtype	data type of send buffer elements (handle)
recvcount	number of elements in receive buffer (integer)
recvtype	data type of receive buffer elements (handle)
root	rank of sending process (integer)
comm	communicator (handle)

Output Parameter

recvbuf	address of receive buffer (choice)
----------------	------------------------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

MPI_ERR_BUFFER

Invalid buffer pointer. Usually a null buffer where one is not valid.

Location

`./src/coll/scatterv.c`

MPI_Send**MPI_Send**

MPI_Send — Performs a basic send

Synopsis

```
int MPI_Send( void *buf, int count, MPI_Datatype datatype, int dest,
              int tag, MPI_Comm comm )
```

Input Parameters

buf	initial address of send buffer (choice)
count	number of elements in send buffer (nonnegative integer)
datatype	datatype of each send buffer element (handle)
dest	rank of destination (integer)
tag	message tag (integer)
comm	communicator (handle)

Notes

This routine may block until the message is received.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

MPI_ERR_TAG

Invalid tag argument. Tags must be non-negative; tags in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_TAG`. The largest tag value is available through the attribute `MPI_TAG_UB`.

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_SOURCE`.

See Also

`MPI_Isend`, `MPI_Bsend`

Location

`./src/pt2pt/send.c`

MPI_Send_init**MPI_Send_init**

MPI_Send_init — Builds a handle for a standard send

Synopsis

```
int MPI_Send_init( void *buf, int count, MPI_Datatype datatype, int dest,
                   int tag, MPI_Comm comm, MPI_Request *request )
```

Input Parameters

buf	initial address of send buffer (choice)
count	number of elements sent (integer)
datatype	type of each element (handle)
dest	rank of destination (integer)
tag	message tag (integer)
comm	communicator (handle) Output Parameter:
request	communication request (handle)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted `MPI_Datatype` (see `MPI_Type_commit`).

`MPI_ERR_RANK`

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_SOURCE`.

`MPI_ERR_TAG`

Invalid tag argument. Tags must be non-negative; tags in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_TAG`. The largest tag value is available through the attribute `MPI_TAG_UB`.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

See Also

`MPI_Start`, `MPI_Startall`, `MPI_Request_free`

Location

`./src/pt2pt/create_send.c`

`MPI_Sendrecv`

`MPI_Sendrecv`

`MPI_Sendrecv` — Sends and receives a message

Synopsis

```
int MPI_Sendrecv( void *sendbuf, int sendcount, MPI_Datatype sendtype,
                  int dest, int sendtag,
                  void *recvbuf, int recvcount, MPI_Datatype recvtype,
                  int source, int recvtag, MPI_Comm comm, MPI_Status *status )
```

Input Parameters

sendbuf	initial address of send buffer (choice)
sendcount	number of elements in send buffer (integer)
sendtype	type of elements in send buffer (handle)
dest	rank of destination (integer)
sendtag	send tag (integer)
recvcount	number of elements in receive buffer (integer)
recvtype	type of elements in receive buffer (handle)
source	rank of source (integer)
recvtag	receive tag (integer)
comm	communicator (handle)

Output Parameters

recvbuf	initial address of receive buffer (choice)
status	status object (Status). This refers to the receive operation.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call
(not even allowed in **MPI_Comm_rank**).

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted **MPI_Datatype** (see **MPI_Type_commit**).

MPI_ERR_TAG

Invalid tag argument. Tags must be non-negative; tags in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_TAG**. The largest tag value is available through the attribute **MPI_TAG_UB**.

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_SOURCE**.

Location

`./src/pt2pt/sendrecv.c`

MPI_Sendrecv_replace

MPI_Sendrecv_replace

MPI_Sendrecv_replace — Sends and receives using a single buffer

Synopsis

```
int MPI_Sendrecv_replace( void *buf, int count, MPI_Datatype datatype,
                         int dest, int sendtag, int source, int recvtag,
                         MPI_Comm comm, MPI_Status *status )
```

Input Parameters

count	number of elements in send and receive buffer (integer)
datatype	type of elements in send and receive buffer (handle)
dest	rank of destination (integer)
sendtag	send message tag (integer)
source	rank of source (integer)
recvtag	receive message tag (integer)
comm	communicator (handle)

Output Parameters

buf	initial address of send and receive buffer (choice)
status	status object (Status)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted MPI_Datatype (see **MPI_Type_commit**).

MPI_ERR_TAG

Invalid tag argument. Tags must be non-negative; tags in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_TAG**. The largest tag value is available through the attribute **MPI_TAG_UB**.

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_SOURCE**.

MPI_ERR_TRUNCATE

Message truncated on receive. The buffer size specified was too small for the received message. This is a recoverable error in the MPICH implementation.

MPI_ERR_INTERN

This error is returned when some part of the MPICH implementation is unable to acquire memory.

Location

`./src/pt2pt/sendrecv_rep.c`

MPI_Ssend**MPI_Ssend**

MPI_Ssend — Basic synchronous send

Synopsis

```
int MPI_Ssend( void *buf, int count, MPI_Datatype datatype,
               int dest, int tag, MPI_Comm comm )
```

Input Parameters

buf	initial address of send buffer (choice)
count	number of elements in send buffer (nonnegative integer)
datatype	datatype of each send buffer element (handle)
dest	rank of destination (integer)
tag	message tag (integer)
comm	communicator (handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in `MPI_Comm_rank`).

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

`MPI_ERR_TAG`

Invalid tag argument. Tags must be non-negative; tags in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_TAG`. The largest tag value is available through the attribute `MPI_TAG_UB`.

`MPI_ERR_RANK`

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (`MPI_Recv`, `MPI_Irecv`, `MPI_Sendrecv`, etc.) may also be `MPI_ANY_SOURCE`.

Location

`./src/pt2pt/ssend.c`

`MPI_Ssend_init`

`MPI_Ssend_init`

`MPI_Ssend_init` — Builds a handle for a synchronous send

Synopsis

```
int MPI_Ssend_init( void *buf, int count, MPI_Datatype datatype, int dest,
                    int tag, MPI_Comm comm, MPI_Request *request )
```

Input Parameters

<code>buf</code>	initial address of send buffer (choice)
<code>count</code>	number of elements sent (integer)
<code>datatype</code>	type of each element (handle)
<code>dest</code>	rank of destination (integer)
<code>tag</code>	message tag (integer)
<code>comm</code>	communicator (handle)

Output Parameter

request communication request (handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted **MPI_Datatype** (see **MPI_Type_commit**).

MPI_ERR_TAG

Invalid tag argument. Tags must be non-negative; tags in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_TAG**. The largest tag value is available through the attribute **MPI_TAG_UB**.

MPI_ERR_RANK

Invalid source or destination rank. Ranks must be between zero and the size of the communicator minus one; ranks in a receive (**MPI_Recv**, **MPI_Irecv**, **MPI_Sendrecv**, etc.) may also be **MPI_ANY_SOURCE**.

Location

`./src/pt2pt/ssend_init.c`

MPI_Start

MPI_Start

MPI_Start — Initiates a communication with a persistent request handle

Synopsis

```
int MPI_Start(
    MPI_Request *request)
```

Input Parameter

request communication request (handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_REQUEST

Invalid **MPI_Request**. Either null or, in the case of a **MPI_Start** or **MPI_Startall**, not a persistent request.

Location

`./src/pt2pt/start.c`

MPI_Startall

MPI_Startall

MPI_Startall — Starts a collection of requests

Synopsis

```
int MPI_Startall( int count, MPI_Request array_of_requests[] )
```

Input Parameters

count list length (integer)

array_of_requests
array of requests (array of handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./src/pt2pt/startall.c
```

MPI_Status_c2f

MPI_Status_c2f

MPI_Status_c2f — Convert a C status to a Fortran status

Synopsis

```
int MPI_Status_c2f( MPI_Status *c_status, MPI_Fint *f_status )
```

Input Parameters

c_status Status value in C (Status)

Output Parameter

f_status Status value in Fortran (Integer)

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

```
./src/misc2/statusc2f.c
```

MPI_Status_set_cancelled

MPI_Status_set_cancelled

MPI_Status_set_cancelled — Set the opaque part of an MPI_Status so that **MPI_Test_cancelled** will return flag

Synopsis

```
int MPI_Status_set_cancelled( MPI_Status *status, int flag )
```

Input Parameters

status	Status to associate count with (Status)
flag	if true indicates that request was cancelled (logical)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

Location

`./src/external/statuscancel.c`

MPI_Status_set_elements

MPI_Status_set_elements

MPI_Status_set_elements — Set the opaque part of an **MPI_Status** so that **MPI_Get_elements** will return count.

Synopsis

```
int MPI_Status_set_elements( MPI_Status *status, MPI_Datatype datatype,
                            int count )
```

Input Parameters

status	Status to associate count with (Status)
datatype	datatype associated with count (handle)
count	number of elements to associate with status (integer)

Location

`./src/external/statuselm.c`

MPI_Test**MPI_Test**

MPI_Test — Tests for the completion of a send or receive

Synopsis

```
int MPI_Test (
    MPI_Request *request,
    int          *flag,
    MPI_Status   *status)
```

Input Parameter

request communication request (handle)

Output Parameter

flag	true if operation completed (logical)
status	status object (Status). May be MPI_STATUS_IGNORE .

Note on status for send operations

For send operations, the only use of status is for **MPI_Test_cancelled** or in the case that there is an error, in which case the **MPI_ERROR** field of status will be set.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_REQUEST

Invalid **MPI_Request**. Either null or, in the case of a **MPI_Start** or **MPI_Startall**, not a persistent request.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

```
./src/pt2pt/test.c
```

MPI_Test_cancelled**MPI_Test_cancelled**

MPI_Test_cancelled — Tests to see if a request was cancelled

Synopsis

```
int MPI_Test_cancelled(
    MPI_Status *status,
    int         *flag)
```

Input Parameter

status status object (Status)

Output Parameter

flag (logical)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

```
./src/pt2pt/testcancel.c
```

MPI_Testall**MPI_Testall**

MPI_Testall — Tests for the completion of all previously initiated communications

Synopsis

```
int MPI_Testall(
    int count,
    MPI_Request array_of_requests[],
    int *flag,
    MPI_Status array_of_statuses[] )
```

Input Parameters

count lists length (integer)
array_of_requests array of requests (array of handles)

Output Parameters

flag (logical)
array_of_statuses array of status objects (array of Status). May be **MPI_STATUSES_IGNORE**.

Notes

flag is true only if all requests have completed. Otherwise, **flag** is false and neither the **array_of_requests** nor the **array_of_statuses** is modified.

Note on status for send operations

For send operations, the only use of status is for **MPI_Test_cancelled** or in the case that there is an error, in which case the **MPI_ERROR** field of status will be set.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_IN_STATUS

The actual error value is in the **MPI_Status** argument. This error class is returned only from the multiple-completion routines (**MPI_Testall**, **MPI_Testany**, **MPI_Testsome**, **MPI_Waitall**, **MPI_Waitany**, and **MPI_Waitsome**). The field **MPI_ERROR** in the status argument contains the error value or **MPI_SUCCESS** (no error and complete) or **MPI_ERR_PENDING** to indicate that the request has not completed.

The MPI Standard does not specify what the result of the multiple completion routines is when an error occurs. For example, in an **MPI_WAITALL**, does the routine wait for all requests to either fail or complete, or does it return immediately (with the MPI definition of immediately, which means independent of actions of other MPI processes)? MPICH has chosen to make the return immediate (alternately, local in MPI terms), and to use the error class **MPI_ERR_PENDING** (introduced in MPI 1.1) to indicate which requests have not completed. In most cases, only one request with an error

will be detected in each call to an MPI routine that tests multiple requests. The requests that have not been processed (because an error occurred in one of the requests) will have their **MPI_ERROR** field marked with **MPI_ERR_PENDING**.

Location

`./src/pt2pt/testall.c`

MPI_Testany

MPI_Testany

MPI_Testany — Tests for completion of any previously initiated communication

Synopsis

```
int MPI_Testany(
    int count,
    MPI_Request array_of_requests[],
    int *index, int *flag,
    MPI_Status *status )
```

Input Parameters

count	list length (integer)
array_of_requests	array of requests (array of handles)

Output Parameters

index	index of operation that completed, or MPI_UNDEFINED if none completed (integer)
flag	true if one of the operations is complete (logical)
status	status object (Status). May be MPI_STATUS_IGNORE .

Note on status for send operations

For send operations, the only use of status is for **MPI_Test_cancelled** or in the case that there is an error, in which case the **MPI_ERROR** field of status will be set.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

Location

`./src/pt2pt/testany.c`

`MPI_Testsome`

`MPI_Testsome`

`MPI_Testsome` — Tests for some given communications to complete

Synopsis

```
int MPI_Testsome(
    int incount,
    MPI_Request array_of_requests[],
    int *outcount,
    int array_of_indices[],
    MPI_Status array_of_statuses[] )
```

Input Parameters

<code>incount</code>	length of <code>array_of_requests</code> (integer)
<code>array_of_requests</code>	array of requests (array of handles)

Output Parameters

<code>outcount</code>	number of completed requests (integer)
<code>array_of_indices</code>	array of indices of operations that completed (array of integers)
<code>array_of_statuses</code>	array of status objects for operations that completed (array of Status). May be <code>MPI_STATUSES_IGNORE</code> .

Note on status for send operations

For send operations, the only use of status is for `MPI_Test_cancelled` or in the case that there is an error, in which case the `MPI_ERROR` field of status will be set.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_IN_STATUS`

The actual error value is in the `MPI_Status` argument. This error class is returned only from the multiple-completion routines (`MPI_Testall`, `MPI_Testany`, `MPI_Testsome`, `MPI_Waitall`, `MPI_Waitany`, and `MPI_Waitsome`). The field `MPI_ERROR` in the status argument contains the error value or `MPI_SUCCESS` (no error and complete) or `MPI_ERR_PENDING` to indicate that the request has not completed.

The MPI Standard does not specify what the result of the multiple completion routines is when an error occurs. For example, in an `MPI_WAITALL`, does the routine wait for all requests to either fail or complete, or does it return immediately (with the MPI definition of immediately, which means independent of actions of other MPI processes)? MPICH has chosen to make the return immediate (alternately, local in MPI terms), and to use the error class `MPI_ERR_PENDING` (introduced in MPI 1.1) to indicate which requests have not completed. In most cases, only one request with an error will be detected in each call to an MPI routine that tests multiple requests. The requests that have not been processed (because an error occurred in one of the requests) will have their `MPI_ERROR` field marked with `MPI_ERR_PENDING`.

Location

`./src/pt2pt/testsome.c`

`MPI_Topo_test`

`MPI_Topo_test`

`MPI_Topo_test` — Determines the type of topology (if any) associated with a communicator

Synopsis

```
int MPI_Topo_test ( MPI_Comm comm, int *top_type )
```

Input Parameter

<code>comm</code>	communicator (handle)
-------------------	-----------------------

Output Parameter

top_type topology type of communicator **comm** (choice).

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_COMM

Invalid communicator. A common error is to use a null communicator in a call (not even allowed in **MPI_Comm_rank**).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

See Also

MPI_Graph_create, **MPI_Cart_create**

Location

`./src/topol/topo_test.c`

MPI_Type_commit

MPI_Type_commit

MPI_Type_commit — Commits the datatype

Synopsis

```
int MPI_Type_commit ( MPI_Datatype *datatype )
```

Input Parameter

datatype datatype (handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted **MPI_Datatype** (see **MPI_Type_commit**).

Location

`./src/pt2pt/type_commit.c`

MPI_Type_contiguous

MPI_Type_contiguous

MPI_Type_contiguous — Creates a contiguous datatype

Synopsis

```
int MPI_Type_contiguous(
    int count,
    MPI_Datatype old_type,
    MPI_Datatype *newtype)
```

Input Parameters

count	replication count (nonnegative integer)
oldtype	old datatype (handle)

Output Parameter

newtype	new datatype (handle)
----------------	-----------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return

value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted `MPI_Datatype` (see `MPI_Type_commit`).

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

Location

`./src/pt2pt/type_contig.c`

`MPI_Type_create_darray`

`MPI_Type_create_darray`

`MPI_Type_create_darray` — Creates a datatype corresponding to a distributed, multidimensional array

Synopsis

```
int MPI_Type_create_darray(int size, int rank, int ndims,
                           int *array_of_gsizes, int *array_of_distrib,
                           int *array_of_dargs, int *array_of_psizes,
                           int order, MPI_Datatype oldtype,
                           MPI_Datatype *newtype)
```

Input Parameters

<code>size</code>	size of process group (positive integer)
<code>rank</code>	rank in process group (nonnegative integer)
<code>ndims</code>	number of array dimensions as well as process grid dimensions (positive integer)
<code>array_of_gsizes</code>	number of elements of type <code>oldtype</code> in each dimension of global array (array of positive integers)
<code>array_of_distrib</code>	distribution of array in each dimension (array of state)

array_of_dargs distribution argument in each dimension (array of positive integers)
array_of_psizes size of process grid in each dimension (array of positive integers)
order array storage order flag (state)
oldtype old datatype (handle)

Output Parameters

newtype new datatype (handle)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./src/misc2/darray.c`

MPI_Type_create_indexed_block	MPI_Type_create_indexed_block
--------------------------------------	--------------------------------------

MPI_Type_create_indexed_block — Creates an indexed datatype with constant sized blocks

Synopsis

```
int MPI_Type_create_indexed_block(
    int count,
    int blocklength,
    int array_of_displacements[],
    MPI_Datatype old_type,
    MPI_Datatype *newtype )
```

Input Parameters

count number of blocks – also number of entries in indices and blocklens
blocklength number of elements in each block (integer)
array_of_displacements displacement of each block in multiples of `old_type` (array of integer)
old_type old datatype (handle)

Output Parameter

newtype new datatype (handle)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

The indices are displacements, and are based on a zero origin. A common error is to do something like to following

```
integer a(100)
integer blens(10), indices(10)
do i=1,10
10    indices(i) = 1 + (i-1)*10
      call MPI_TYPE_CREATE_INDEXED_BLOCK(10,1,indices,MPI_INTEGER,newtype,ierr)
      call MPI_TYPE_COMMIT(newtype,ierr)
      call MPI_SEND(a,1,newtype,...)
```

expecting this to send `a(1),a(11),...` because the indices have values `1,11,...`. Because these are *displacements* from the beginning of `a`, it actually sends `a(1+1),a(1+11),...`.

If you wish to consider the displacements as indices into a Fortran array, consider declaring the Fortran array with a zero origin

```
integer a(0:99)
```

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

Location

```
./src/misc2/type_blkkind.c
```

`MPI_Type_create_subarray`

`MPI_Type_create_subarray`

`MPI_Type_create_subarray` — Creates a datatype describing a subarray of a multidimensional array

Synopsis

```
int MPI_Type_create_subarray(
    int ndims,
    int *array_of_sizes,
    int *array_of_subsizes,
    int *array_of_starts,
    int order,
    MPI_Datatype oldtype,
    MPI_Datatype *newtype)
```

Input Parameters

ndims number of array dimensions (positive integer)
array_of_sizes number of elements of type **oldtype** in each dimension of the full array (array of positive integers)
array_of_subsizes number of elements of type **oldtype** in each dimension of the subarray (array of positive integers)
array_of_starts starting coordinates of the subarray in each dimension (array of nonnegative integers)
order array storage order flag (state)
oldtype old datatype (handle)

Output Parameters

newtype new datatype (handle)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./src/misc2/subarray.c`

MPI_Type_extent

MPI_Type_extent

MPI_Type_extent — Returns the extent of a datatype

Synopsis

```
int MPI_Type_extent( MPI_Datatype datatype, MPI_Aint *extent )
```

Input Parameters

datatype datatype (handle)

Output Parameter

extent datatype extent (integer)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted **MPI_Datatype** (see **MPI_Type_commit**).

Location

`./src/pt2pt/type_extent.c`

MPI_Type_free

MPI_Type_free

MPI_Type_free — Frees the datatype

Synopsis

```
int MPI_Type_free ( MPI_Datatype *datatype )
```

Input Parameter

datatype datatype that is freed (handle)

Predefined types

The MPI standard states that (in Opaque Objects)

`MPI provides certain predefined opaque objects and predefined, static handles to these objects. Such objects may not be destroyed.`

Thus, it is an error to free a predefined datatype. The same section makes it clear that it is an error to free a null datatype.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted `MPI_Datatype` (see `MPI_Type_commit`).

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

Location

`./src/pt2pt/type_free.c`

`MPI_Type_get_contents`

`MPI_Type_get_contents`

`MPI_Type_get_contents` — Retrieves the actual arguments used in the creation call for a datatype

Synopsis

```
int MPI_Type_get_contents(
    MPI_Datatype datatype,
    int max_integers,
    int max_addresses,
    int max_datatypes,
    int *array_of_integers,
    MPI_Aint *array_of_addresses,
    MPI_Datatype *array_of_datatypes)
```

Input Parameters

datatype datatype to access (handle)
max_integers number of elements in array_of_integers (non-negative integer)
max_addresses number of elements in array_of_addresses (non-negative integer)
max_datatypes number of elements in array_of_datatypes (non-negative integer)

Output Parameters

array_of_integers contains integer arguments used in constructing datatype (array of integers)
array_of_addresses contains address arguments used in constructing datatype (array of integers)
array_of_datatypes contains datatype arguments used in constructing datatype (array of handles)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./src/external/type_get_cont.c`

MPI_Type_get_envelope

MPI_Type_get_envelope

MPI_Type_get_envelope — Returns information on the number and type of input arguments used in the call that created datatype

Synopsis

```
int MPI_Type_get_envelope(
    MPI_Datatype datatype,
    int *num_integers,
    int *num_addresses,
    int *num_datatypes,
    int *combiner)
```

Input Parameters

datatype datatype to access (handle)

Output Parameters

num_integers number of input integers used in the call constructing combiner (nonnegative integer)
num_addresses number of input addresses used in the call constructing combiner (nonnegative integer)
num_datatypes number of input datatypes used in the call constructing combiner (nonnegative integer)
combiner combiner (state)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Location

`./src/external/type_get_env.c`

MPI_Type_hindexed

MPI_Type_hindexed

MPI_Type_hindexed — Creates an indexed datatype with offsets in bytes

Synopsis

```
int MPI_Type_hindexed(
    int count,
    int blocklens[],
    MPI_Aint indices[],
    MPI_Datatype old_type,
    MPI_Datatype *newtype )
```

Input Parameters

count number of blocks – also number of entries in indices and blocklens
blocklens number of elements in each block (array of nonnegative integers)
indices byte displacement of each block (array of **MPI_Aint**)
old_type old datatype (handle)

Output Parameter

newtype new datatype (handle)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Also see the discussion for `MPI_Type_indexed` about the `indices` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted `MPI_Datatype` (see `MPI_Type_commit`).

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

Location

`./src/pt2pt/type Hind.c`

`MPI_Type_hvector`

`MPI_Type_hvector`

`MPI_Type_hvector` — Creates a vector (strided) datatype with offset in bytes

Synopsis

```
int MPI_Type_hvector(
    int count,
    int blocklen,
    MPI_Aint stride,
    MPI_Datatype old_type,
    MPI_Datatype *newtype )
```

Input Parameters

<code>count</code>	number of blocks (nonnegative integer)
--------------------	--

blocklength	number of elements in each block (nonnegative integer)
stride	number of bytes between start of each block (integer)
old_type	old datatype (handle)

Output Parameter

newtype	new datatype (handle)
----------------	-----------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted `MPI_Datatype` (see `MPI_Type_commit`).

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

Location

`./src/pt2pt/type_hvec.c`

`MPI_Type_indexed`

`MPI_Type_indexed`

`MPI_Type_indexed` — Creates an indexed datatype

Synopsis

```
int MPI_Type_indexed(
    int count,
    int blocklens[],
    int indices[],
```

```
MPI_Datatype old_type,
MPI_Datatype *newtype )
```

Input Parameters

count	number of blocks – also number of entries in indices and blocklens
blocklens	number of elements in each block (array of nonnegative integers)
indices	displacement of each block in multiples of old_type (array of integers)
old_type	old datatype (handle)

Output Parameter

newtype	new datatype (handle)
----------------	-----------------------

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran. The indices are displacements, and are based on a zero origin. A common error is to do something like to following

```
integer a(100)
integer blens(10), indices(10)
do i=1,10
    blens(i) = 1
10   indices(i) = 1 + (i-1)*10
call MPI_TYPE_INDEXED(10,blens,indices,MPI_INTEGER,newtype,ierr)
call MPI_TYPE_COMMIT(newtype,ierr)
call MPI_SEND(a,1,newtype,...)
```

expecting this to send **a(1),a(11),...** because the indices have values **1,11,...**. Because these are *displacements* from the beginning of **a**, it actually sends **a(1+1),a(1+11),...**.

If you wish to consider the displacements as indices into a Fortran array, consider declaring the Fortran array with a zero origin

```
integer a(0:99)
```

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_ERR_COUNT

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

MPI_ERR_INTERN

This error is returned when some part of the MPICH implementation is unable to acquire memory.

Location

```
./src/pt2pt/type_ind.c
```

MPI_Type_lb**MPI_Type_lb**

MPI_Type_lb — Returns the lower-bound of a datatype

Synopsis

```
int MPI_Type_lb ( MPI_Datatype datatype, MPI_Aint *displacement )
```

Input Parameters

datatype datatype (handle)

Output Parameter

displacement displacement of lower bound from origin, in bytes (integer)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted MPI_Datatype (see `MPI_Type_commit`).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

```
./src/pt2pt/type_lb.c
```

MPI_Type_size**MPI_Type_size**

MPI_Type_size — Return the number of bytes occupied by entries in the datatype

Synopsis

```
int MPI_Type_size ( MPI_Datatype datatype, int *size )
```

Input Parameters

datatype datatype (handle)

Output Parameter

size datatype size (integer)

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_TYPE

Invalid datatype argument. May be an uncommitted **MPI_Datatype** (see **MPI_Type_commit**).

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

`./src/pt2pt/type_size.c`

MPI_Type_struct	MPI_Type_struct
MPI_Type_struct — Creates a struct datatype	

Synopsis

```
int MPI_Type_struct(
    int count,
    int blocklens[],
    MPI_Aint indices[],
    MPI_Datatype old_types[],
    MPI_Datatype *newtype )
```

Input Parameters

count	number of blocks (integer) – also number of entries in arrays <code>array_of_types</code> , <code>array_of_displacements</code> and <code>array_of_blocklengths</code>
blocklens	number of elements in each block (array)
indices	byte displacement of each block (array)
old_types	type of elements in each block (array of handles to datatype objects)

Output Parameter

newtype	new datatype (handle)
----------------	-----------------------

Notes

If an upperbound is set explicitly by using the MPI datatype `MPI_UB`, the corresponding index must be positive.

The MPI standard originally made vague statements about padding and alignment; this was intended to allow the simple definition of structures that could be sent with a count greater than one. For example,

```
struct { int a; char b; } foo;
```

may have `sizeof(foo) > sizeof(int) + sizeof(char)`; for example, `sizeof(foo) == 2*sizeof(int)`. The initial version of the MPI standard defined the extent of a datatype as including an *epsilon* that would have allowed an implementation to make the extent an MPI datatype for this structure equal to `2*sizeof(int)`. However, since different systems might define different paddings, there was much discussion by the MPI Forum about what was the correct value of epsilon, and one suggestion was to define epsilon as zero. This would have been the best thing to do in MPI 1.0, particularly since the `MPI_UB` type allows the user to easily set the end of the structure. Unfortunately, this change did not make it into the final document. Currently, this routine does not add any padding, since the amount of padding needed is determined by the compiler that the user is using to build their code, not the compiler used to construct the MPI library. A later version of MPICH may provide for some natural choices of padding (e.g., multiple of the size of the largest basic member), but users are advised to never depend on this, even with

vendor MPI implementations. Instead, if you define a structure datatype and wish to send or receive multiple items, you should explicitly include an `MPI_UB` entry as the last member of the structure. For example, the following code can be used for the structure `foo`

```
blen[0] = 1; indices[0] = 0; oldtypes[0] = MPI_INT;
blen[1] = 1; indices[1] = &foo.b - &foo; oldtypes[1] = MPI_CHAR;
blen[2] = 1; indices[2] = sizeof(foo); oldtypes[2] = MPI_UB;
MPI_Type_struct( 3, blen, indices, oldtypes, &newtype );
```

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted `MPI_Datatype` (see `MPI_Type_commit`).

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_INTERN`

This error is returned when some part of the MPICH implementation is unable to acquire memory.

Location

`./src/pt2pt/type_struct.c`

`MPI_Type_ub`

`MPI_Type_ub`

`MPI_Type_ub` — Returns the upper bound of a datatype

Synopsis

```
int MPI_Type_ub ( MPI_Datatype datatype, MPI_Aint *displacement )
```

Input Parameters

datatype datatype (handle)

Output Parameter

displacement displacement of upper bound from origin, in bytes (integer)

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted `MPI_Datatype` (see `MPI_Type_commit`).

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

Location

`./src/pt2pt/type_ub.c`

`MPI_Type_vector`

`MPI_Type_vector`

`MPI_Type_vector` — Creates a vector (strided) datatype

Synopsis

```
int MPI_Type_vector(
    int count,
    int blocklen,
    int stride,
    MPI_Datatype old_type,
    MPI_Datatype *newtype )
```

Input Parameters

count	number of blocks (nonnegative integer)
blocklength	number of elements in each block (nonnegative integer)
stride	number of elements between start of each block (integer)
oldtype	old datatype (handle)

Output Parameter

newtype	new datatype (handle)
----------------	-----------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Location

`./src/pt2pt/type_vec.c`

MPI_Unpack

MPI_Unpack

MPI_Unpack — Unpack a datatype into contiguous memory

Synopsis

```
int MPI_Unpack ( void *inbuf, int insize, int *position,
                  void *outbuf, int outcount, MPI_Datatype datatype,
                  MPI_Comm comm )
```

Input Parameters

inbuf	input buffer start (choice)
insize	size of input buffer, in bytes (integer)
position	current position in bytes (integer)
outcount	number of items to be unpacked (integer)
datatype	datatype of each output data item (handle)
comm	communicator for packed message (handle)

Output Parameter

outbuf	output buffer start (choice)
---------------	------------------------------

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_COMM`

Invalid communicator. A common error is to use a null communicator in a call
(not even allowed in `MPI_Comm_rank`).

`MPI_ERR_COUNT`

Invalid count argument. Count arguments must be non-negative; a count of zero is often valid.

`MPI_ERR_TYPE`

Invalid datatype argument. May be an uncommitted `MPI_Datatype` (see `MPI_Type_commit`).

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

See Also

`MPI_Pack`, `MPI_Pack_size`

Location

`./src/pt2pt/unpack.c`

`MPI_Wait`

`MPI_Wait`

`MPI_Wait` — Waits for an MPI send or receive to complete

Synopsis

```
int MPI_Wait (
    MPI_Request *request,
    MPI_Status *status)
```

Input Parameter

request request (handle)

Output Parameter

status status object (Status) . May be **MPI_STATUS_IGNORE**.

Note on status for send operations

For send operations, the only use of status is for **MPI_Test_cancelled** or in the case that there is an error, in which case the **MPI_ERROR** field of status will be set.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_REQUEST

Invalid **MPI_Request**. Either null or, in the case of a **MPI_Start** or **MPI_Startall**, not a persistent request.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

Location

`./src/pt2pt/wait.c`

MPI_Waitall**MPI_Waitall**

MPI_Waitall — Waits for all given communications to complete

Synopsis

```
int MPI_Waitall(
    int count,
    MPI_Request array_of_requests[],
    MPI_Status array_of_statuses[] )
```

Input Parameters

count lists length (integer)
array_of_requests array of requests (array of handles)

Output Parameter

array_of_statuses array of status objects (array of Status). May be **MPI_STATUSES_IGNORE**

Note on status for send operations

For send operations, the only use of status is for **MPI_Test_cancelled** or in the case that there is an error, in which case the **MPI_ERROR** field of status will be set.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_REQUEST

Invalid **MPI_Request**. Either null or, in the case of a **MPI_Start** or **MPI_Startall**, not a persistent request.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

MPI_ERR_IN_STATUS

The actual error value is in the **MPI_Status** argument. This error class is returned only from the multiple-completion routines (**MPI_Testall**, **MPI_Testany**, **MPI_Testsome**, **MPI_Waitall**, **MPI_Waitany**, and **MPI_Waitsome**). The field **MPI_ERROR** in the status argument contains the error value or **MPI_SUCCESS** (no error and complete) or **MPI_ERR_PENDING** to indicate that the request has not completed.

The MPI Standard does not specify what the result of the multiple completion routines is when an error occurs. For example, in an **MPI_WAITALL**, does the routine wait for all requests to either fail or complete, or does it return immediately (with the MPI definition of immediately, which means

independent of actions of other MPI processes)? MPICH has chosen to make the return immediate (alternately, local in MPI terms), and to use the error class **MPI_ERR_PENDING** (introduced in MPI 1.1) to indicate which requests have not completed. In most cases, only one request with an error will be detected in each call to an MPI routine that tests multiple requests. The requests that have not been processed (because an error occurred in one of the requests) will have their **MPI_ERROR** field marked with **MPI_ERR_PENDING**.

MPI_ERR_PENDING

Pending request (not an error). See **MPI_ERR_IN_STATUS**. This value indicates that the request is not complete nor has it encountered a detected error.

Location

`./src/pt2pt/waitall.c`

MPI_Waitany

MPI_Waitany

MPI_Waitany — Waits for any specified send or receive to complete

Synopsis

```
int MPI_Waitany(
    int count,
    MPI_Request array_of_requests[],
    int *index,
    MPI_Status *status )
```

Input Parameters

count	list length (integer)
array_of_requests	array of requests (array of handles)

Output Parameters

index	index of handle for operation that completed (integer). In the range 0 to count -1. In Fortran, the range is 1 to count .
status	status object (Status). May be MPI_STATUS_IGNORE .

Notes

If all of the requests are **MPI_REQUEST_NULL**, then **index** is returned as **MPI_UNDEFINED**, and **status** is returned as an empty status.

Note on status for send operations

For send operations, the only use of status is for **MPI_Test_cancelled** or in the case that there is an error, in which case the **MPI_ERROR** field of status will be set.

Notes for Fortran

All MPI routines in Fortran (except for `MPI_WTIME` and `MPI_WTICK`) have an additional argument `ierr` at the end of the argument list. `ierr` is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the `call` statement.

All MPI objects (e.g., `MPI_Datatype`, `MPI_Comm`) are of type `INTEGER` in Fortran.

Errors

All MPI routines (except `MPI_Wtime` and `MPI_Wtick`) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with `MPI_Errhandler_set`; the predefined error handler `MPI_ERRORS_RETURN` may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

`MPI_SUCCESS`

No error; MPI routine completed successfully.

`MPI_ERR_REQUEST`

Invalid `MPI_Request`. Either null or, in the case of a `MPI_Start` or `MPI_Startall`, not a persistent request.

`MPI_ERR_ARG`

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., `MPI_ERR_RANK`).

Location

`./src/pt2pt/waitany.c`

`MPI_Waitsome`

`MPI_Waitsome`

`MPI_Waitsome` — Waits for some given communications to complete

Synopsis

```
int MPI_Waitsome(
    int incount,
    MPI_Request array_of_requests[],
    int *outcount,
    int array_of_indices[],
    MPI_Status array_of_statuses[] )
```

Input Parameters

<code>incount</code>	length of <code>array_of_requests</code> (integer)
<code>array_of_requests</code>	array of requests (array of handles)

Output Parameters

outcount number of completed requests (integer)
array_of_indices array of indices of operations that completed (array of integers)
array_of_statuses array of status objects for operations that completed (array of Status). May be **MPI_STATUSES_IGNORE**.

Notes

The array of indices are in the range 0 to **incount** - 1 for C and in the range 1 to **incount** for Fortran.

Null requests are ignored; if all requests are null, then the routine returns with **outcount** set to **MPI_UNDEFINED**.

Note on status for send operations

For send operations, the only use of status is for **MPI_Test_cancelled** or in the case that there is an error, in which case the **MPI_ERROR** field of status will be set.

Notes for Fortran

All MPI routines in Fortran (except for **MPI_WTIME** and **MPI_WTICK**) have an additional argument **ierr** at the end of the argument list. **ierr** is an integer and has the same meaning as the return value of the routine in C. In Fortran, MPI routines are subroutines, and are invoked with the **call** statement.

All MPI objects (e.g., **MPI_Datatype**, **MPI_Comm**) are of type **INTEGER** in Fortran.

Errors

All MPI routines (except **MPI_Wtime** and **MPI_Wtick**) return an error value; C routines as the value of the function and Fortran routines in the last argument. Before the value is returned, the current MPI error handler is called. By default, this error handler aborts the MPI job. The error handler may be changed with **MPI_Errhandler_set**; the predefined error handler **MPI_ERRORS_RETURN** may be used to cause error values to be returned. Note that MPI does *not* guarantee that an MPI program can continue past an error.

MPI_SUCCESS

No error; MPI routine completed successfully.

MPI_ERR_REQUEST

Invalid **MPI_Request**. Either null or, in the case of a **MPI_Start** or **MPI_Startall**, not a persistent request.

MPI_ERR_ARG

Invalid argument. Some argument is invalid and is not identified by a specific error class (e.g., **MPI_ERR_RANK**).

MPI_ERR_IN_STATUS

The actual error value is in the **MPI_Status** argument. This error class is returned only from the multiple-completion routines (**MPI_Testall**, **MPI_Testany**, **MPI_Testsome**, **MPI_Waitall**, **MPI_Waitany**, and **MPI_Waitsome**). The field **MPI_ERROR** in the status argument contains the error value or **MPI_SUCCESS** (no error and complete) or **MPI_ERR_PENDING** to indicate that the request has not completed.

The MPI Standard does not specify what the result of the multiple completion routines is when an error occurs. For example, in an **MPI_WAITALL**, does the routine wait for all requests to either fail or

complete, or does it return immediately (with the MPI definition of immediately, which means independent of actions of other MPI processes)? MPICH has chosen to make the return immediate (alternately, local in MPI terms), and to use the error class **MPI_ERR_PENDING** (introduced in MPI 1.1) to indicate which requests have not completed. In most cases, only one request with an error will be detected in each call to an MPI routine that tests multiple requests. The requests that have not been processed (because an error occurred in one of the requests) will have their **MPI_ERROR** field marked with **MPI_ERR_PENDING**.

Location

```
./src/pt2pt/waitsome.c
```

MPI_Wtick

MPI_Wtick

MPI_Wtick — Returns the resolution of **MPI_Wtime**

Synopsis

```
double MPI_Wtick()
```

Return value

Time in seconds of resolution of **MPI_Wtime**

Notes for Fortran

This is a function, declared as **DOUBLE PRECISION MPI_WTICK()** in Fortran.

Location

```
./src/env/wtick.c
```

MPI_Wtime

MPI_Wtime

MPI_Wtime — Returns an elapsed time on the calling processor

Synopsis

```
double MPI_Wtime()
```

Return value

Time in seconds since an arbitrary time in the past.

Notes

This is intended to be a high-resolution, elapsed (or wall) clock. See `MPI_WTICK` to determine the resolution of `MPI_WTIME`. If the attribute `MPI_WTIME_IS_GLOBAL` is defined and true, then the value is synchronized across all processes in `MPI_COMM_WORLD`.

Notes for Fortran

This is a function, declared as `DOUBLE PRECISION MPI_WTIME()` in Fortran.

See Also

also: `MPI_Wtick`, `MPI_Attr_get`

Location

`./src/env/wtime.c`

3 MPE routines

CLOG_Finalize

CLOG_Finalize

`CLOG_Finalize` — Finalize CLOG logging

Synopsis

```
void CLOG_Finalize( void )
```

Location

`./mpe/src/clog.c`

CLOG_Init

CLOG_Init

`CLOG_Init` — Initialize for CLOG logging

Synopsis

```
void CLOG_Init( void )
```

Location

```
./mpe/src/clog.c
```

CLOG_Output**CLOG_Output**

CLOG_Output — output a block of the log. The byte ordering, if needed, will be performed in this function using the conversion routines got from Petsc.

Synopsis

```
void CLOG_output( buf )
double *buf;
```

Location

```
./mpe/src/clog_merge.c
```

CLOG_commtype**CLOG_commtype**

CLOG_commtype — print communicator creation event type

Synopsis

```
void CLOG_commtype( etype )
int etype;
```

etype event type for communicator creation event

Location

```
./mpe/src/clog_util.c
```

CLOG_cput**CLOG_cput**

CLOG_cput — move a log record from one of the input buffers to the output

Synopsis

```
void CLOG_cput( ptr )
double **ptr;
```

This function moves records from one of the three buffers being merged into the output buffer. When the output buffer is filled, it is sent to the parent. A separate output routine handles output on the root. If the input buffer is emptied (endblock record is read) and corresponds to a child, a new buffer is received from the child. When an endlog record is read on the input buffer, the number

of sources is decremented and the time is set to positive infinity so that the empty input source will never have the lowest time.

At entry we assume that *p is pointing to a log record that is not an end-of-block record, and that outbuf is pointing to a buffer that has room in it for the record. We ensure that these conditions are met on exit as well, by sending (or writing, if we are the root) and receiving blocks as necessary.

Input parameters

pointer to the record to be moved into the output buffer

Location

`./mpe/src/clog_merge.c`

CLOG_csync

CLOG_csync

CLOG_csync — synchronize clocks for adjusting times in merge

Synopsis

```
void CLOG_csync( root, diff );
int root;
double diff[];
```

This version is sequential and non-scalable. The root process serially synchronizes with each slave, using the first algorithm in Gropp, "Scalable clock synchronization on distributed processors without a common clock". The array is calculated on the root but broadcast and returned on all processes.

Inout Parameters

root	process to serve as master
timediffs	array of doubles to be filled in

Location

`./mpe/src/clog_merge.c`

CLOG_get_new_event

CLOG_get_new_event

CLOG_get_new_event — obtain unused event id

Synopsis

```
int CLOG_get_new_event( void )
```

Location

`./mpe/src/clog.c`

CLOG_get_new_state**CLOG_get_new_state**

CLOG_get_new_state — obtain unused state id

Synopsis

```
int CLOG_get_new_state( void )
```

Location

./mpe/src/clog.c

CLOG_init_buffers**CLOG_init_buffers**

CLOG_init_buffers — initialize necessary buffers for clog logging.

Synopsis

```
void CLOG_init_buffers( void )
```

Location

./mpe/src/clog.c

CLOG_mergelogs**CLOG_mergelogs**

CLOG_mergelogs — merge individual logfiles into one via messages

Synopsis

```
void CLOG_mergelogs( shift, execfilename, logtype )
int shift;
char *execfilename;
int logtype;
```

first argument says whether to do time-shifting or not second arg is filename
 On process 0 in MPI_COMM_WORLD, collect logs from other processes and merge them with own log. Timestamps are assumed to be already adjusted on both incoming logs and the master's. On the other processes, fill in length and process id's and send them, a block at a time, to the master. The master writes out the merged log.

Location

./mpe/src/clog_merge.c

CLOG_mergend**CLOG_mergend**

CLOG_mergend — finish log processing

Synopsis

```
void CLOG_mergend()
```

Location

```
./mpe/src/clog_merge.c
```

CLOG_msctype**CLOG_msctype**

CLOG_msctype — print communication event type

Synopsis

```
void CLOG_msctype( etype )
int etype;
```

etype event type for pt2pt communication event

Location

```
./mpe/src/clog_util.c
```

CLOG_newbuff**CLOG_newbuff**

CLOG_newbuff — get and initialize new block of buffer

Synopsis

```
void CLOG_newbuff( CLOG_BLOCK **bufptr )
```

Input Parameter

bufptr pointer to be filled in with address of new block

Location

```
./mpe/src/clog.c
```

CLOG_nodebuffer2disk**CLOG_nodebuffer2disk**

CLOG_nodebuffer2disk — dump buffers into temporary log file.

Synopsis

```
void CLOG_nodebuffer2disk( void )
```

Location

`./mpe/src/clog.c`

CLOG_prodbuf**CLOG_prodbuf**

CLOG_prodbuf — postprocess a buffer of log records before merging

Synopsis

```
void CLOG_prodbuf( buf )
double *buf;
```

This function fills in fields in log records that were left out during actual logging to save memory accesses. Typical fields are the process id and the lengths of records that are known by predefined type. This is also where we will adjust timestamps.

Input parameter

address of the buffer to be processed

Location

`./mpe/src/clog_merge.c`

CLOG_reclen**CLOG_reclen**

CLOG_reclen — get length (in doubles) of log record by type

Synopsis

```
int CLOG_reclen( type )
int type;
```

Location

`./mpe/src/clog_util.c`

CLOG_rectype **CLOG_rectype**

CLOG_rectype — print log record type

Synopsis

```
void CLOG_rectype( type )
int type;
```

rtype record type

Location

```
./mpe/src/clog_util.c
```

CLOG_reinit_buff **CLOG_reinit_buff**

CLOG_reinit_buff — reads CLOG_BLOCKS from temporary logfile into memory.

Synopsis

```
void CLOG_reinit_buff( )
```

Location

```
./mpe/src/clog_merge.c
```

CLOG_treesetup **CLOG_treesetup**

CLOG_treesetup — locally determine parent and children in binary tree

Synopsis

```
void CLOG_treesetup( self, numprocs, myparent, mylchild, myrchild)
int self, numprocs, *myparent, *mylchild, *myrchild;
```

Input parameters

self	calling process's id
np	total number of processes in tree
Output parameters	
parent	parent in binary tree (or -1 if root)
lchild	left child in binary tree (or -1 if none)
rchild	right child in binary tree (or -1 if none)

Location

`./mpe/src/clog_merge.c`

MPE_Add_RGB_color	MPE_Add_RGB_color
--------------------------	--------------------------

MPE_Add_RGB_color — Adds a color to the colormap given its RGB values

Synopsis

```
#include "mpe.h"
int MPE_Add_RGB_color( graph, red, green, blue, mapping )
MPE_XGraph graph;
int red, green, blue;
MPE_Color *mapping;
```

Input Parameters

graph	MPE graphics handle
red, green, blue	color levels from 0 to 65535

Output Parameter

mapping	index of the new color
----------------	------------------------

Return Values

-1	maxcolors too large (equal to numcolors)
MPE_SUCCESS	successful
mapping	index of the new color

Notes

This call adds a color cell to X11's color table, increments maxcolors (the index), and writes it to the mapping parameter.

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, MPI_Comm, MPE_XGraph and MPE_Color, are of type INTEGER in Fortran.

Location

`./mpe/src/mpe_graphics.c`

MPE_CaptureFile

MPE_CaptureFile

MPE_CaptureFile — Sets the base filename used to capture output from updates

Synopsis

```
#include "mpe.h"
int MPE_CaptureFile( handle, fname, freq )
MPE_XGraph handle;
char *fname;
int freq;
```

Input Parameters

handle	MPE graphics handle
fname	base file name (see below)
freq	Frequency of updates

Return Values

MPE_ERR_LOW_MEM

malloc for copy of the filename (fname) failed

MPE_ERR_BAD_ARGS

`handle` parameter is bad

MPE_SUCCESS

success

Notes

The output is written in xwd format to `fname%d`, where `%d` is the number of the file (starting from zero).

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, MPI_Comm, MPE_XGraph and MPE_Color, are of type INTEGER in Fortran.

Additional Notes for Fortran Interface

The trailing blanks in Fortran CHARACTER string argument will be ignored.

Location

```
./mpe/src/mpe_graphics.c
```

MPE_Close_graphics**MPE_Close_graphics**

MPE_Close_graphics — Closes an X11 graphics device

Synopsis

```
#include "mpe.h"
int MPE_Close_graphics( handle )
MPE_XGraph *handle;
```

Input Parameter

handle MPE graphics handle.

Return Values

MPE_ERR_BAD_ARGS	handle parameter is bad
MPE_SUCCESS	success

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, MPI_Comm, MPE_XGraph and MPE_Color, are of type INTEGER in Fortran.

Location

```
./mpe/src/mpe_graphics.c
```

MPE_Comm_global_rank**MPE_Comm_global_rank**

MPE_Comm_global_rank — Returns the rank in MPI_COMM_WORLD for a given (communicator,rank) pair

Synopsis

```
void MPE_Comm_global_rank( comm, rank, grank )
MPI_Comm comm;
int      rank, *grank;
```

Input Parameters

comm	Communicator
rank	Rank in comm

Output Parameters

grank	Rank in comm world
--------------	--------------------

Location

`./mpe/src/getgrank.c`

MPE_Counter_create**MPE_Counter_create**

MPE_Counter_create — create and initialize shared counter (process)

Synopsis

```
int MPE_Counter_create( oldcomm, smaller_comm, counter_comm )
MPI_Comm oldcomm, *smaller_comm, *counter_comm;
```

Input Parameter

oldcomm	Communicator to
----------------	-----------------

Output Parameters

smaller_comm	
---------------------	--

counter_comm	Duplicate of oldcomm
---------------------	-----------------------------

Location

`./mpe/src/mpe_counter.c`

MPE_Counter_free**MPE_Counter_free**

MPE_Counter_free — free communicators associated with counter

Synopsis

```
int MPE_Counter_free( smaller_comm, counter_comm )
MPI_Comm *smaller_comm;
MPI_Comm *counter_comm;
```

Location

```
./mpe/src/mpe_counter.c
```

MPE_Counter_nxtval**MPE_Counter_nxtval**

MPE_Counter_nxtval — obtain next value from shared counter, and update

Synopsis

```
int MPE_Counter_nxtval(counter_comm, value)
MPI_Comm counter_comm;
int *value;
```

Location

```
./mpe/src/mpe_counter.c
```

MPE_DecomP1d**MPE_DecomP1d**

MPE_DecomP1d — Compute a balanced decomposition of a 1-D array

Synopsis

```
int MPE_DecomP1d( n, size, rank, s, e )
int n, size, rank, *s, *e;
```

Input Parameters

n	Length of the array
size	Number of processors in decomposition
rank	Rank of this processor in the decomposition ($0 \leq \text{rank} < \text{size}$)

Output Parameters

s,e Array indices are $\text{s}:\text{e}$, with the original array considered as $1:\text{n}$.

Location

```
./mpe/src/decomp.c
```

MPE_Describe_event**MPE_Describe_event**

MPE_Describe_event — Create log record describing an event type

Synopsis

```
int MPE_Describe_event( event, name )
int event;
char *name;
```

Input Parameters

event Event number
name String describing the event.

See Also

MPE_Log_get_event_number

Location

`./mpe/src/mpe_log.c`

MPE_Describe_state

MPE_Describe_state

MPE_Describe_state — Create log record describing a state

Synopsis

```
int MPE_Describe_state( start, end, name, color )
int start, end;
char *name, *color;
```

Input Parameters

start event number for the start of the state
end event number for the end of the state
name Name of the state
color color to display the state in

Notes

Adds string containing a state def to the logfile. The format of the definition is (in ALOG)

`(LOG_STATE_DEF) 0 s e 0 0 "color" "name"`

States are added to a log file by calling **MPE_Log_event** for the start and end event numbers.

See Also

MPE_Log_get_event_number

Location

`./mpe/src/mpe_log.c`

MPE_Draw_circle

MPE_Draw_circle

MPE_Draw_circle — Draws a circle

Synopsis

```
#include "mpe.h"
int MPE_Draw_circle( graph, centerx, centery, radius, color )
MPE_XGraph graph;
int centerx, centery, radius;
MPE_Color color;
```

Input Parameters

graph	MPE graphics handle
centerx	horizontal center point of the circle
centery	vertical center point of the circle
radius	radius of the circle
color	color of the circle

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, MPI_Comm, MPE_XGraph and MPE_Color, are of type INTEGER in Fortran.

Location

`./mpe/src/mpe_graphics.c`

MPE_Draw_line

MPE_Draw_line

MPE_Draw_line — Draws a line on an X11 display

Synopsis

```
#include "mpe.h"
int MPE_Draw_line( handle, x1, y_1, x2, y_2, color )
MPE_XGraph handle;
int      x1, y_1, x2, y_2;
MPE_Color color;
```

Input Parameters

handle	MPE graphics handle
x1,y_1	pixel position of one end of the line to draw. Coordinates are upper-left origin (standard X11)
x2,y_2	pixel position of the other end of the line to draw. Coordinates are upper-left origin (standard X11)
color	Color <i>index</i> value. See MPE_MakeColorArray . By default, the colors MPE_WHITE , MPE_BLACK , MPE_RED , MPE_YELLOW , MPE_GREEN , MPE_CYAN , MPE_BLUE , MPE_MAGENTA , MPE_AQUAMARINE , MPE_FORESTGREEN , MPE_ORANGE , MPE_VIOLET , MPE_BROWN , MPE_PINK , MPE_CORAL and MPE_GRAY are defined.

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, MPI_Comm, MPE_XGraph and MPE_Color, are of type INTEGER in Fortran.

Location

`./mpe/src/mpe_graphics.c`

MPE_Draw_logic

MPE_Draw_logic

MPE_Draw_logic — Sets logical operation for laying down new pixels

Synopsis

```
#include "mpe.h"
int MPE_Draw_logic( graph, function )
MPE_XGraph graph;
int function;
```

Input Parameters

graph	MPE graphics handle
function	integer specifying one of the following: MPE_LOGIC_COPY - no logic, just copy the pixel MPE_LOGIC_XOR - xor the new pixel with the existing one and many more... see mpe_graphics.h

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, MPI_Comm, MPE_XGraph and MPE_Color, are of type INTEGER in Fortran.

Location

`./mpe/src/mpe_graphics.c`

MPE_Draw_point

MPE_Draw_point

MPE_Draw_point — Draws a point on an X Windows display

Synopsis

```
#include "mpe.h"
int MPE_Draw_point( handle, x, y, color )
MPE_XGraph handle;
int      x, y;
MPE_Color color;
```

Input Parameters

handle	MPE graphics handle
x,y	pixel position to draw. Coordinates are upper-left origin (standard X11)
color	Color <i>index</i> value. See MPE_MakeColorArray . By default, the colors MPE_WHITE , MPE_BLACK , MPE_RED , MPE_YELLOW , MPE_GREEN , MPE_CYAN , MPE_BLUE , MPE_MAGENTA , MPE_AQUAMARINE , MPE_FORESTGREEN , MPE_ORANGE , MPE_VIOLET , MPE_BROWN , MPE_PINK , MPE_CORAL and MPE_GRAY are defined.

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, MPI_Comm, MPE_XGraph and MPE_Color, are of type INTEGER in Fortran.

Location

`./mpe/src/mpe_graphics.c`

MPE_Draw_points

MPE_Draw_points

MPE_Draw_points — Draws points on an X Windows display

Synopsis

```
#include "mpe.h"
int MPE_Draw_points( handle, points, npoints )
MPE_XGraph handle;
MPE_Point *points;
int npoints;
```

Input Parameters

handle	MPE graphics handle
points	list of points to draw
npoints	number of points to draw

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, MPI_Comm, MPE_XGraph and MPE_Color, are of type INTEGER in Fortran.

Location

./mpe/src/mpe_graphics.c

MPE_Draw_string	MPE_Draw_string
------------------------	------------------------

MPE_Draw_string — Draw a text string

Synopsis

```
#include "mpe.h"
int MPE_Draw_string( graph, x, y, color, string )
MPE_XGraph graph;
int x, y;
MPE_Color color;
char *string;
```

Input Parameters

graph	MPE graphics handle
x	x-coordinate of the origin of the string
y	y-coordinate of the origin of the string
color	color of the text
string	text string to be drawn

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, MPI_Comm, MPE_XGraph and MPE_Color, are of type INTEGER in Fortran.

Additional Notes for Fortran Interface

The trailing blanks in Fortran CHARACTER string argument will be ignored.

Location

`./mpe/src/mpe_graphics.c`

MPE_Fill_circle

MPE_Fill_circle

MPE_Fill_circle — Fills a circle

Synopsis

```
#include "mpe.h"
int MPE_Fill_circle( graph, centerx, centery, radius, color )
MPE_XGraph graph;
int centerx, centery, radius;
MPE_Color color;
```

Input Parameters

graph	MPE graphics handle
centerx	horizontal center point of the circle
centery	vertical center point of the circle
radius	radius of the circle
color	color of the circle

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, MPI_Comm, MPE_XGraph and MPE_Color, are of type INTEGER in Fortran.

Location

`./mpe/src/mpe_graphics.c`

MPE_Fill_rectangle

MPE_Fill_rectangle

MPE_Fill_rectangle — Draws a filled rectangle on an X11 display

Synopsis

```
#include "mpe.h"
int MPE_Fill_rectangle( handle, x, y, w, h, color )
MPE_XGraph handle;
int      x, y, w, h;
MPE_Color color;
```

Input Parameters

handle	MPE graphics handle
x,y	pixel position of the upper left (low coordinate) corner of the rectangle to draw.
w,h	width and height of the rectangle
color	Color <i>index</i> value. See MPE_MakeColorArray . By default, the colors MPE_WHITE , MPE_BLACK , MPE_RED , MPE_YELLOW , MPE_GREEN , MPE_CYAN , MPE_BLUE , MPE_MAGENTA , MPE_AQUAMARINE , MPE_FORESTGREEN , MPE_ORANGE , MPE_VIOLET , MPE_BROWN , MPE_PINK , MPE_CORAL and MPE_GRAY are defined.

Notes

This uses the X11 definition of width and height, so you may want to add 1 to both of them.

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, MPI_Comm, MPE_XGraph and MPE_Color, are of type INTEGER in Fortran.

Location

`./mpe/src/mpe_graphics.c`

MPE_Finish_log

MPE_Finish_log

MPE_Finish_log — Send log to master, who writes it out

Synopsis

```
int MPE_Finish_log( filename )
char *filename;
```

Notes

This routine dumps a logfile in alog or clog format. It is collective over **MPI_COMM_WORLD**. The default is alog format. To generate clog output, set the environment variable **MPE_LOG_FORMAT** to CLOG.

Location

`./mpe/src/mpe_log.c`

MPE_GetTags

MPE_GetTags

MPE_GetTags — Returns tags that can be used in communication with a communicator

Synopsis

```
int MPE_GetTags( comm_in, ntags, comm_out, first_tag )
MPI_Comm comm_in, *comm_out;
int      ntags, *first_tag;
```

Input Parameters

comm_in Input communicator
ntags Number of tags

Output Parameters

comm_out Output communicator. May be **comm_in**.
first_tag First tag available

Returns

MPI_SUCCESS on success, MPI error class on failure.

Notes

This routine returns the requested number of tags, with the tags being **first_tag**, **first_tag+1**, ..., **first_tag+ntags-1**.

These tags are guaranteed to be unique within **comm_out**.

See Also

[MPE_ReturnTags](#)

Location

[./mpe/src/prvtags.c](#)

MPE_Get_mouse_press

MPE_Get_mouse_press

MPE_Get_mouse_press — Waits for mouse button press

Synopsis

```
#include "mpe.h"
int MPE_Get_mouse_press( graph, x, y, button )
MPE_XGraph graph;
int *x, *y, *button;
```

Input Parameter

graph MPE graphics handle

Output Parameters

x	horizontal coordinate of the point where the mouse button was pressed
y	vertical coordinate of the point where the mouse button was pressed
button	which button was pressed: MPE_BUTTON[1-5]

Notes

This routine waits for mouse button press, blocking until the mouse button is pressed inside this MPE window. When pressed, returns the coordinate relative to the upper right of this MPE window and the button that was pressed.

Location

`./mpe/src/xmouse.c`

MPE_IO_Stdout_to_file

MPE_IO_Stdout_to_file

MPE_IO_Stdout_to_file — Re-direct stdout to a file

Synopsis

```
void MPE_IO_Stdout_to_file( char *name, int mode )
```

Parameters

name	Name of file. If it contains %d , this value will be replaced with the rank of the process in MPI_COMM_WORLD .
mode	Mode to open the file in (see the man page for open). A common value is 0644 (Read/Write for owner, Read for everyone else). Note that this value is <i>anded</i> with your current umask value.

Notes

Some systems may complain when standard output (**stdout**) is closed.

Location

`./mpe/src/mpe_io.c`

MPE_Iget_mouse_press

MPE_Iget_mouse_press

MPE_Iget_mouse_press — Checks for mouse button press

Synopsis

```
#include "mpe.h"
int MPE_Iget_mouse_press( graph, x, y, button, wasPressed )
MPE_XGraph graph;
int *x, *y, *button, *wasPressed;
```

Input Parameter

graph MPE graphics handle

Output Parameters

x	horizontal coordinate of the point where the mouse button was pressed
y	vertical coordinate of the point where the mouse button was pressed
button	which button was pressed: MPE_BUTTON[1-5]
wasPressed	1 if the button was pressed, 0 if not

Notes

Checks if the mouse button has been pressed inside this MPE window. If pressed, returns the coordinate relative to the upper right of this MPE window and the button that was pressed.

Location

`./mpe/src/xmouse.c`

MPE_Init_log

MPE_Init_log

MPE_Init_log — Initialize for logging

Synopsis

`int MPE_Init_log()`

Notes

Initializes the MPE logging package. This must be called before any of the other MPE logging routines. It is collective over `MPI_COMM_WORLD`

See Also

`MPE_Finish_log`

Location

`./mpe/src/mpe_log.c`

MPE_Initialized_logging

MPE_Initialized_logging

MPE_Initialized_logging — Indicate whether `MPE_Init_log` or `MPE_Finish_log` have been called.

Synopsis

```
int MPE_Initialized_logging ()
```

Returns

0 if MPE_Init_log has not been called, 1 if MPE_Init_log has been called but MPE_Finish_log has not been called, and 2 otherwise.

Location

```
./mpe/src/mpe_log.c
```

MPE_Line_thickness
MPE_Line_thickness

MPE_Line_thickness — Sets thickness of lines

Synopsis

```
#include "mpe.h"
int MPE_Line_thickness( graph, thickness )
MPE_XGraph graph;
int thickness;
```

Input Parameters

graph	MPE graphics handle
thickness	integer specifying how many pixels wide lines should be

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, MPI_Comm, MPE_XGraph and MPE_Color, are of type INTEGER in Fortran.

Location

```
./mpe/src/mpe_graphics.c
```

MPE_Log_event
MPE_Log_event

MPE_Log_event — Logs an event

Synopsis

```
int MPE_Log_event(event,data,string)
int event, data;
char *string;
```

Input Parameters

event	Event number
data	Integer data value
string	Optional string describing event

Location

`./mpe/src/mpe_log.c`

MPE_Log_get_event_number**MPE_Log_get_event_number**

MPE_Log_get_event_number — Gets an unused event number

Synopsis

```
int MPE_Log_get_event_number( )
```

Returns

A value that can be provided to `MPE_Describe_event` or `MPE_Describe_state` which will define an event or state not used before.

Notes

This routine is provided to allow packages to ensure that they are using unique event numbers. It relies on all packages using this routine.

Location

`./mpe/src/mpe_log.c`

MPE_Log_receive**MPE_Log_receive**

MPE_Log_receive — log the sending of a message

Synopsis

```
int MPE_Log_receive( otherParty, tag, size )
int otherParty, tag, size;
```

Location

./mpe/src/mpe_log.c

MPE_Log_send

MPE_Log_send

MPE_Log_send — Logs the sending of a message

Synopsis

```
int MPE_Log_send( otherParty, tag, size )
int otherParty, tag, size;
```

Location

./mpe/src/mpe_log.c

MPE_Make_color_array

MPE_Make_color_array

MPE_Make_color_array — Makes an array of color indices

Synopsis

```
#include "mpe.h"
int MPE_Make_color_array( handle, ncolors, array )
MPE_XGraph handle;
int      ncolors;
MPE_Color array[];
```

Input Parameters

handle	MPE graphics handle
nc	Number of colors

Output Parameter

array	Array of color indices
--------------	------------------------

Notes

The new colors for a uniform distribution in hue space and replace the existing colors *except* for `MPE_WHITE` and `MPE_BLACK`.

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, `MPI_Comm`, `MPE_XGraph` and `MPE_Color`, are of type INTEGER in Fortran.

Location

`./mpe/src/mpe_graphics.c`

<code>MPE_Num_colors</code>	<code>MPE_Num_colors</code>
<code>MPE_Num_colors</code> — Gets the number of available colors	

Synopsis

```
#include "mpe.h"
int MPE_Num_colors( handle, nc )
MPE_XGraph handle;
int      *nc;
```

Input Parameter

`handle` MPE graphics handle

Output Parameter

`nc` Number of colors available on the display.

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, `MPI_Comm`, `MPE_XGraph` and `MPE_Color`, are of type INTEGER in Fortran.

Location

`./mpe/src/mpe_graphics.c`

MPE_Open_graphics	MPE_Open_graphics
--------------------------	--------------------------

MPE_Open_graphics — (collectively) opens an X Windows display

Synopsis

```
#include "mpe.h"
int MPE_Open_graphics( handle, comm, display, x, y, w, h, is_collective )
MPE_XGraph *handle;
MPI_Comm    comm;
char        display[MPI_MAX_PROCESSOR_NAME+4];
int         x, y;
int         w, h;
int         is_collective;
```

Input Parameters

comm	Communicator of participating processes
display	Name of X window display. If null, display will be taken from the DISPLAY variable on the process with rank 0 in comm . If that is either undefined, or starts with w ":" , then the value of display is ‘hostname’:0
x,y	position of the window. If (-1,-1), then the user should be asked to position the window (this is a window manager issue).
w,h	width and height of the window, in pixels.
is_collective	true if the graphics operations are collective; this allows the MPE graphics operations to make fewer connections to the display. If false, then all processes in the communicator comm will open the display; this could exceed the number of connections that your X window server allows. Not yet implemented.

Output Parameter

handle	Graphics handle to be given to other MPE graphics routines.
---------------	---

Notes

This is a collective routine. All processes in the given communicator must call it, and it has the same semantics as **MPI_BARRIER** (that is, other collective operations can not cross this routine).

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, MPI_Comm, MPE_XGraph and MPE_Color, are of type INTEGER in Fortran.

Additional Notes for Fortran Interface

If Fortran **display** argument is an empty string, "", display will be taken from the DISPLAY variable on the process with rank 0 in **comm**. The trailing blanks in Fortran CHARACTER string argument will be ignored.

Location

`./mpe/src/mpe_graphics.c`

MPE_Print_datatype_pack_action

MPE_Print_datatype_pack_action

MPE_Print_datatype_pack_action — Prints the operations performed in an pack of a datatype

Synopsis

```
int MPE_Print_datatype_pack_action( fp, count, type, in_offset, out_offset )
FILE          *fp;
int           count;
MPI_Datatype  type;
int           in_offset, out_offset;
```

Input Parameters

fp	FILE pointer for output
count	Count of datatype
type	MPI Datatype
in_offset,out_offset	offsets for input and output buffer. Should be 0 for most uses.

Notes

This prints on the selected file the operations that the MPICH implementation will take when packing a buffer.

Location

`./mpe/src/examine.c`

MPE_Print_datatype_unpack_action

MPE_Print_datatype_unpack_action

MPE_Print_datatype_unpack_action — Prints the operations performed in an unpack of a datatype

Synopsis

```
int MPE_Print_datatype_unpack_action( fp, count, type, in_offset, out_offset )
FILE          *fp;
int           count;
MPI_Datatype  type;
int           in_offset, out_offset;
```

Input Parameters

fp	FILE pointer for output
count	Count of datatype
type	MPI Datatype
in_offset,out_offset	offsets for input and output buffer. Should be 0 for most uses.

Notes

This prints on the selected file the operations that the MPICH implementation will take when unpacking a buffer.

Location

`./mpe/src/examine.c`

MPE_ReturnTags

MPE_ReturnTags

MPE_ReturnTags — Returns tags allocated with MPE_GetTags.

Synopsis

```
int MPE_ReturnTags( comm, first_tag, ntags )
MPI_Comm comm;
int      first_tag, ntags;
```

Input Parameters

comm	Communicator to return tags to
first_tag	First of the tags to return
ntags	Number of tags to return.

See Also

`MPE_GetTags`

Location

`./mpe/src/prvtags.c`

MPE_Seq_begin

MPE_Seq_begin

MPE_Seq_begin — Begins a sequential section of code.

Synopsis

```
void MPE_Seq_begin( MPI_Comm comm, int ng )
```

Input Parameters

- comm** Communicator to sequentialize.
ng Number in group. This many processes are allowed to execute at the same time.
 Usually one.

Notes

MPE_Seq_begin and **MPE_Seq_end** provide a way to force a section of code to be executed by the processes in rank order. Typically, this is done with

```
MPE_Seq_begin( comm, 1 );
<code to be executed sequentially>
MPE_Seq_end( comm, 1 );
```

Often, the sequential code contains output statements (e.g., `printf`) to be executed. Note that you may need to flush the I/O buffers before calling **MPE_Seq_end**; also note that some systems do not propagate I/O in any order to the controlling terminal (in other words, even if you flush the output, you may not get the data in the order that you want).

Location

```
./mpe/src/mpe_seq.c
```

MPE_Seq_end

MPE_Seq_end

MPE_Seq_end — Ends a sequential section of code.

Synopsis

```
void MPE_Seq_end( MPI_Comm comm, int ng )
```

Input Parameters

- comm** Communicator to sequentialize.
ng Number in group. This many processes are allowed to execute at the same time.
 Usually one.

Notes

See **MPE_Seq_begin** for more details.

Location

```
./mpe/src/mpe_seq.c
```

MPE_Start_log**MPE_Start_log**

MPE_Start_log — Begin logging of events

Synopsis

```
int MPE_Start_log()
```

Location

```
./mpe/src/mpe_log.c
```

MPE_Stop_log**MPE_Stop_log**

MPE_Stop_log — Stop logging events

Synopsis

```
int MPE_Stop_log()
```

Location

```
./mpe/src/mpe_log.c
```

MPE_TagsEnd**MPE_TagsEnd**

MPE_TagsEnd — Returns the private keyval.

Synopsis

```
int MPE_TagsEnd()
```

Notes

This routine is provided to aid in cleaning up all of the allocated storage in and MPI program. Normally, this routine does *not* need to be called. If it is, it should be called immediately before **MPI_Finalize**.

Location

```
./mpe/src/privtags.c
```

MPE_Update**MPE_Update**

MPE_Update — Updates an X11 display

Synopsis

```
#include "mpe.h"
int MPE_Update( handle )
MPE_XGraph handle;
```

Input Parameter

handle MPE graphics handle.

Note

Only after an **MPE_Update** can you count on seeing the results of MPE drawing routines. This is caused by the buffering of graphics requests for improved performance.

Notes For Fortran Interface

The Fortran interface to this routine is different from its C counterpart and it has an additional argument, ierr, at the end of the argument list, i.e. the returned function value (the error code) in C interface is returned as the additional argument in Fortran interface. The Fortran interface is invoked with the CALL statement.

All MPI and MPE objects, MPI_Comm, MPE_XGraph and MPE_Color, are of type INTEGER in Fortran.

Location

```
./mpe/src/mpe_graphics.c
```